
YEKTA light



INSTALLATION GUIDE

Clip Studio Paint on Windows

A floating Yekta Light window that sits on top of Clip Studio Paint. No installer — unzip and run.

REQUIREMENTS

Before you start

- Windows 10 or 11, 64-bit.
- The file `YektaLight-Windows.zip` (about 115 MB).
- Any version of Clip Studio Paint.

INSTALL

Unzip and run

1. Right-click `YektaLight-Windows.zip` ▸ **Extract All...** and choose a permanent place, for example `Documents\Yekta Light`. Do not run it from inside the zip.
2. Open the extracted folder `YektaLight-win32-x64` and double-click **Yekta Light.exe**.
3. Windows SmartScreen may say *"Windows protected your PC"* because the app is new and not yet code-signed. Click **More info ▸ Run anyway**. You only need to do this once.
4. Optional: right-click **Yekta Light.exe ▸ Show more options ▸ Send to ▸ Desktop (create shortcut)**, or pin it to the taskbar.

> Yekta Light remembers its window size and position. Place it next to your canvas once and it returns there every time.

UPDATE & REMOVE

Managing the app

- **Update:** close the app, delete the old folder, extract the new zip in the same place.
- **Uninstall:** close the app and delete the folder (and any shortcut). Nothing else is installed on your system.

USING IT WITH CLIP STUDIO PAINT

Getting colors into CSP

Clip Studio Paint does not allow third-party panels, so Yekta Light runs as a small window that stays on top of Clip Studio. You bring colors over in one of two ways:



"Big" palette — easy to eyedrop

1 · Screen eyedropper (recommended)

Clip Studio can pick a color from anywhere on the screen with its **Obtain screen color** command. Assign it a key once (search "Obtain screen color" in **Shortcut Settings**), then press the key and click the big swatch, the 3D form or any palette color in Yekta Light.

Turn on Big in the Light Families row to get large swatches that are easy to hit.

2 · HEX code

Every pick is copied to the clipboard as HEX (for example `#E8A58A`). Paste it wherever your color dialog accepts HEX.

Keep it on top

The Pin button in the header keeps the window above Clip Studio. Turn it off to let the window go behind.

TROUBLESHOOTING

If something is off

PROBLEM	FIX
"Windows protected your PC"	More info ▸ Run anyway (see step 3).
Antivirus quarantine	Some antivirus tools flag new unsigned apps. Restore the file and add the folder as an exception.
Window hidden behind CSP	Turn on **Pin** in the Yekta Light header.