



Common Component

Badge

Banner

Bottom Navigation

Bottom Sheet

Buttons

Box Button

Capsule Button

Floating Action Button

Icon button

Text Button

Chips

Controls

Dialog

Empty

Text Inputs

List Header

Search Bar

Page Indicator

Popup

Profile

Progress Indicator

Spinner

Tabs

Top Navigation

Video Player

Contents Component

Card

Image Grid

List


Chatroom Component

Flex Message

Capsule Button

The Capsule button moves the content to the scroll position when there is new content. It disappears when tapped.

Anatomy



1. Button background

This is the background that covers the largest area, and it displays the characteristics of the button.

2. Text area

This shows the content of the button.

3. Image area (Optional)

You can display related images, icons, or profiles.

States

Active



This is an active state.


Pressed



This is a status in which a user is pressing the button to execute an action.

Types

Two types of capsule buttons, Blue and Mono, are provided based on the highlighting status.



Green




Use a conspicuous highlighting color.

Mono




Use a weaker highlighting color than the blue type.
Or use a strong highlighting color with a dark background.



Do

Select the type based on the highlighting status of the button to provide. The Blue type is used as a strong highlighting color if used on a normal white background.




Do

The Mono type is used as a stronger highlighting color if it is placed in a dark background or image.

Usage


You can use Capsule buttons in the content areas of various services.

General usage



Use for services where the content area is scrolled vertically.

Available Combinations




- You can use together with an avatar image.
- This is used to show the user profile in most cases.
- You can use it together with an thumbnail image.

- In most cases, this is used if related to image content

Interaction


Tap the Capsule button to be scrolled to the area to check the content.

To the above contents



- The Capsule button is at the top, and the screen is scrolled up to check the content when tapped.
- The Capsule button disappears right after scrolling is complete.
- The Capsule button disappears if a user reaches the content corresponding to the Capsule button by scrolling directly.

To the below contents




- The Capsule button is at the bottom, and the screen is scrolled to the bottom to check the content when tapped.
- The Capsule button disappears right after scrolling is complete.
- The Capsule button disappears if a user reaches the content corresponding to the Capsule button by scrolling directly.

Placement


Capsule buttons are located above ordinary plane components.

Top Placement






If the position to be scrolled is at the top of the current scroll position, place the button at the uppermost part of the content area and at the bottom of fixed components, such as Top Navigation. Design QA is required because the margin is not included in the component.

Bottom Placement




If the position to be scrolled is at the bottom of the current scroll position, place the button at the bottommost part of the content area and at the top of fixed components, such as Bottom Navigation or toolbar. Design QA is required because the margin is not included in the component.





Do

Place Capsule buttons above ordinary plane components.




Don't

Do not place Capsule buttons in the center area, except for at the top and bottom of the content area.

Design spec

Design customization of Capsule buttons is not allowed.



Keep in mind that Capsule buttons have different spacing between the UI elements inside the button depending on the type.

Box Button

Floating Action Button