



Common Component

Badge

Banner

Bottom Navigation

Bottom Sheet

Buttons

Chips

Controls

Dialog

Empty

Text Inputs

List Header

Search Bar

Page Indicator

Popup

Profile

Progress Indicator

Spinner

Tabs

Top Navigation

Video Player

Contents Component

Card

Image Grid

List


Chatroom Component

Flex Message

Chips

Chips are components that briefly display an attribute or action.

Anatomy



1. Container area


Composed of a plane (filled) or a contour (stroke) as a background area that contains chip elements. The container width can be determined based on the label area.

2. Image area (Optional)

is an area where a profile or thumbnail can be displayed.


3. Label area

The chip content is displayed as text, and an auxiliary icon, etc. can be selectively displayed together.




Do

Display an attribute or action on the label clearly.



Don't

You cannot use an ellipsis on the label.




Caution



Avoid using line breaks on the label.


Types

The Component Type is classified according to the usability of chips.




- Action type is used for the purpose of executing or setting up actions related to the content.
- The Filter type is used for the purpose of filtering the content.
- The Choice type is used for the purpose of selecting one of the options related to the content. Default selection values are normally provided, and exposed by applying the contour color to the selected option.







Do
Multiple selection is possible in case of using the filter type.



Do
The selection is canceled if a chip selected in the filter type is selected again.



Don't
Multiple selections are not possible in case of using the Choice type. Use the filter type for the multiple selection feature.




Do
Only single selection is possible in case of using the choice type. If another chip is selected in a state of having a selected chip already, the selected chip will be deselected automatically.

State


	Action	Filter	Choice	Description
Deselected				Default state of not being selected A deselected state
Selected	The action occurs when tapped.			A state of being selected by tapping

Usage

Filter type - General




Popular keywords




Use by displaying an attribute or action briefly. Content filtering is possible.

Filter type - Multi



- Both single selections and multiple selections can be used.
- The sub-items of the chip may be changed to dynamic depending on the chip selected by the user.

Choice type



Stickers download by...

Everyone

Men

Women

Between the ages of...

All ages

10 to 19

20 to 29

30 to 39

40 and above

OK

Use by listing the options that can be selected by users as chip components in the currently set option.


Action type

A mobile app interface showing a news feed. At the top, there's a status bar with the time 9:41 and signal/battery icons. Below that is a search bar with a magnifying glass icon and a close button. A navigation bar contains tabs: 'All' (selected), 'Friends', 'Chats', 'Messages', and 'News'. The main content area displays two news items. The first item has a title 'Lorem Ipsum is simply dummy text of the printing and typesetting ...', a short paragraph of Lorem Ipsum text, a timestamp '6min ago · LINE News', a 'Related 5' link, and three colored chips labeled 'Lorem', 'Human Drama', and 'ABCDEFGHI'. The second item has a title 'Contrary to popular belief, Lorem Ipsum is not simply random text ...', a paragraph about Richard McClintock, a timestamp '6min ago · LINE News', and a small image of a plant.


Use dynamically based on the context of the content.

Placement

General




- List the chips from left to right.
- You can place to enable line break or swipe.
- Place on the next line if the width of the next chip is longer than the margin remaining on the screen when placing a line break.
- When placing a swipe function, place so it can be recognized as a swipeable area.




Do

Place on the next line if the width of the next chip is longer than the remaining margin.



Don't

You cannot use it by splitting a chip.



Caution

When placing a swipe function, this should be placed so it can be recognized as a swipeable area by users. When placing a swipe function, place by changing the order of selected chips or joining them so users can clearly recognize the selected items.