



Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation


Segmented Control

Bottom Navigation

Floating Action Button

Floating action buttons are placed at the top layer and used to trigger important actions.


Anatomy



1. Main Button Container
2. Icon
3. Button Label
4. Child Button Container
5. Child Button

Element Patterns and Types

Circle Floating Button



Overlays

Popup

Snackbar

Toast Overlay


Tooltip

Bottom Sheet

Pulldown Menu


Systems

LIFF View



- Expandable Floating Button: Button for multiple actions. Selecting this button will show the sub actions with child buttons.
- Single Action Floating Button: Button for one action. Selecting this button will run the action associated with the button.
- Expandable Floating Button: Button for multiple actions. Selecting this button will show the sub actions with child buttons.

Pill Floating Button




- Use this button to induce additional actions, such as Refresh.
- Patterns vary depending on the left icon options.
- Place this button at the top, bottom, or center of the screen.
- Selecting the button will run the action associated with the button immediately (works same as the single action floating button of circular type).

Behavior

Circle Floating Button


Expandable Floating Button






- Available in two states: Default and expanded.
- Selecting the main button will change the status to Expanded, and child buttons will be displayed along with the dimmer.
- In the Expanded status, the main button's icon is changed to the close icon.

Pill Floating Button




- Selecting the button will run the action immediately.
- See [Skeleton](#) Behavior.

Usage




Don't
Do not use non-intuitive icons.



Don't
Do not add text inside the floating button.


Don't
Do not combine this with additional elements.



Don't
Do not use more than five buttons except for main button.


Design Specs

Styles



Element	Properties
	Fill: Changeable

		◦ Default: ldsg-color-brand-primary
1	Main Button Container	• Shadow: Changeable ◦ Default : ldsg-shadow-on-white-200 • Size: Unchangeable
2	Main Button Icon	• Fill: Changeable ◦ Default: ldsg-color-white • Size: Unchangeable
3	Child Button Label	• Fill: Changeable ◦ Default: ldsg-color-white • Shadow: Changeable ◦ Default : ldsg-shadow-on-white-200 • Size: Unchangeable
4	Child Button Container	• Fill: Changeable ◦ Default: ldsg-color-white • Shadow: Changeable ◦ Default : ldsg-shadow-on-white-200 • Size: Unchangeable
5	Child Button Icon	• Fill: Changeable ◦ Default: ldsg-color-black • Size: Unchangeable



Element	Properties
	• Fill: Changeable

1 Container

- Default: ldsg-color-white
- Border Color: Changeable
 - Default : ldsg-color-gray-300
- Border Radius: Changeable
 - Default: ldsg-radius-circle
- Shadow : Changeable
 - Default: ldsg-shadow-on-white-200
- Padding: Unchangeable
- Width: Auto Width
- Height: Unchangeable, Fixed Height

2 Icon(Optional)

- Fill: Changeable
 - Default
 - Enabled: ldsg-color-black
- Size: Unchangeable

3 Button Label

- Typography: Changeable
 - Default: ldsg-typography-text-s-100
- Color: Changeable
 - Default: ldsg-color-black