

Global Family Service

Foundation

Components

Case Studies

v 3.5

Buttons

Action Button

Floating Action Button

Icon Button

Contents

Avatar

Tag

Image Grid

Skeleton

Video Player

Indicators

Badge

Page Controller

Page Indicator

Progress Indicator

Inputs

Checkbox

Chip

Radio Button

Slider

Stepper

Switch

Text Area

Text Input

Pulldown

Navigations

Tab

Tab - Expanded Tab List

Side Drawer

Footer

Top Navigation

Segmented Control

Bottom Navigation

Radio Button

Radio buttons allow you to select one out of two or more items in the same group.

Anatomy

1

Control Text Label

Please enter a Guide description

2

3

1. Container

2. Text Label

3. Description (Optional)

Element Patterns and Types

|             |         |          |       |
|-------------|---------|----------|-------|
| Description | True    | False    |       |
| States      | Enabled | Disabled | Error |
| Selected    | True    | False    |       |

Description

Overlays

- Popup
- Snackbar
- Toast Overlay
- Tooltip
- Bottom Sheet
- Pulldown Menu

Systems

LIFF View

Text Only

☒ Control Text Label

☐ Control Text Label

Text + Description

☒ Control Text Label  
Please enter a Guide description

☐ Control Text Label  
Please enter a Guide description

You can select whether to use a description. Description is not used by default.

States

Selected

Unselected

Enabled

☒ Control Text Label

☐ Control Text Label

Disabled

☐ Control Text Label

☐ Control Text Label

Hover

☒ Control Text Label

☐ Control Text Label

Pressed

☒ Control Text Label

☐ Control Text Label

Error

☒ Control Text Label

☐ Control Text Label

A radio button may have the normal and selected states. The states may be used in duplicate except for the "Disabled" state. The "Hover" and "Pressed" states are not provided in the design library, and the states are automatically applied during development.

General States

|          |                                                                                                                                                                                                                                          |
|----------|------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------------|
| Enabled  | <ul style="list-style-type: none"><li>Indicates that the component is available.</li></ul>                                                                                                                                               |
| Disabled | <ul style="list-style-type: none"><li>Indicates that the component is not available.</li><li>Option changes are not available in this state.</li></ul>                                                                                   |
| Hover    | <ul style="list-style-type: none"><li>A state indicating that the mouse cursor is placed over an element, which is available only in PC and web environments.</li><li>This state is not available when "Disabled" is selected.</li></ul> |
| Pressed  | <ul style="list-style-type: none"><li>Provided for the "Mouse Down" or "Touch Down" states.</li><li>This state is not available when "Disabled" is selected.</li></ul>                                                                   |

Error

- Indicates an error when a required selection has not been made or a wrong option has been selected. Users can change the selection states.

Select States


Selected

- Indicates that a checkbox has been selected.


Unselected


- Indicates that a checkbox has not been selected.
- This option is used by default.

Behavior




A state where no selection has been made can be set as the default, but once a selection has been made, you cannot deselect the selected item to revert to the original state where no selection has been made.






- ☐ Sausage 1
- ☐ Sausage 2




- ☐ Sausage 1
- ☐ Sausage 2




You can select one item in the group.

## Usage



### Do

Because radio buttons are mutually exclusive, you can select only one item in one group.



### Don't

You cannot select multiple items.