




Make sure vmware workstation version is 25






New Virtual Machine Wizard
Guest Operating System Installation
A virtual machine is like a physical computer; it needs an operating system. How will you install the guest operating system?
Install from:
Installer disc:
No drives available
Installer disc image file (iso):
C:\CC\Softwares\Eucalyptus faststart-3.4.1.iso
Browse...
I will install the operating system later.
The virtual machine will be created with a blank hard disk.
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Select a Guest Operating System
Which operating system will be installed on this virtual machine?
Guest operating system
Microsoft Windows
Linux
VMware ESX
Other
Version
CentOS 6
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Name the Virtual Machine
What name would you like to use for this virtual machine?
Virtual machine name:
CentOS 6
Location:
C:\Users\Lenovo\Documents\Virtual Machines\CentOS 6
Browse...
The default location can be changed at Edit > Preferences.
< Back
Next >
Cancel



New Virtual Machine Wizard
Processor Configuration
Specify the number of processors for this virtual machine.
Processors
Number of processors:
1
Number of cores per processor:
2
Total processor cores:
2
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Memory for the Virtual Machine
How much memory would you like to use for this virtual machine?
Specify the amount of memory allocated to this virtual machine. The memory size must be a multiple of 4 MB.
128 GB
64 GB
32 GB
16 GB
8 GB
4 GB
2 GB
1 GB
512 MB
256 MB
128 MB
64 MB
32 MB
16 MB
8 MB
4 MB
Memory for this virtual machine:
4096
MB
Maximum recommended memory:
13.2 GB
Recommended memory:
1 GB
Guest OS recommended minimum:
512 MB
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Network Type
What type of network do you want to add?
Network connection
Use bridged networking
Give the guest operating system direct access to an external Ethernet network. The guest must have its own IP address on the external network.
Use network address translation (NAT)
Give the guest operating system access to the host computer's Wi-Fi or Ethernet network connection using the host's IP address.
Use host-only networking
Connect the guest operating system to a private virtual network on the host computer.
Do not use a network connection
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Select I/O Controller Types
Which SCSI controller type would you like to use for SCSI virtual disks?
I/O controller types
SCSI Controller:
BusLogic (Maximum disk capacity: 2 TB)
LSI Logic (Recommended)
LSI Logic SAS
Paravirtualized SCSI
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Select a Disk Type
What kind of disk do you want to create?
Virtual disk type
IDE
SCSI (Recommended)
SATA
NVMe
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Select a Disk
Which disk do you want to use?
Disk
Create a new virtual disk
A virtual disk is composed of one or more files on the host file system, which will appear as a single hard disk to the guest operating system. Virtual disks can easily be copied or moved on the same host or between hosts.
Use an existing virtual disk
Choose this option to reuse a previously configured disk.
Use a physical disk (for advanced users)
Choose this option to give the virtual machine direct access to a local hard disk. Requires administrator privileges.
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Specify Disk Capacity
How large do you want this disk to be?
Maximum disk size (GB):
60.0
Recommended size for CentOS 6: 20 GB
Allocate all disk space now.
Allocating the full capacity can enhance performance but requires all of the physical disk space to be available right now. If you do not allocate all the space now, the virtual disk starts small and grows as you add data to it.
Store virtual disk as a single file
Split virtual disk into multiple files
Splitting the disk makes it easier to move the virtual machine to another computer but may reduce performance with very large disks.
Help
< Back
Next >
Cancel


New Virtual Machine Wizard
Specify Disk File
Where would you like to store the disk file?
Disk file
A 60 GB virtual disk be created using multiple disk files. The disk files will be automatically named based on this file name.
CentOS 6.vmdk
Browse...
Help
< Back
Next >
Cancel



New Virtual Machine Wizard
Ready to Create Virtual Machine
Click Finish to create the virtual machine. Then you can install CentOS 6.
The virtual machine will be created with the following settings:
Name: CentOS 6
Location: C:\Users\Lenovo\Documents\Virtual Machines\CentO...
Version: Workstation 25H2
Operating System: CentOS 6
Hard Disk: 60 GB, Split
Memory: 4096 MB
Network Adapter: NAT
Other Devices: 2 CPU cores, CD/DVD, USB Controller, Sound Card
Customize Hardware...
< Back
Finish
Cancel



Virtual Machine Settings
Hardware
Options
Device
Summary
Memory
4 GB
Processors
2
Hard Disk (SCSI)
60 GB
CD/DVD (IDE)
Auto detect
Network Adapter
NAT
USB Controller
Present
Sound Card
Auto detect
Display
Auto detect
Add...
Remove
Device status
Connected
Connect at power on
Connection
Use physical drive:
Auto detect
Use ISO image file:
C:\CC\Softwares\Eucalyptus faststart-3.4.1.iso
Browse...
Advanced...
OK
Cancel
Help
Primary IP address: Network information is not available


Virtual Machine Settings
Hardware
Options
Device
Summary
Memory
4 GB
Processors
2
Hard Disk (SCSI)
60 GB
CD/DVD (IDE)
Using file C:\CC\Softwares\E...
Network Adapter
NAT
USB Controller
Present
Sound Card
Auto detect
Display
Auto detect
Add...
Remove
Processors
Number of processors:
1
Number of cores per processor:
2
Total processor cores:
2
Virtualization engine
Virtualize Intel VT-x/EPT or AMD-V/RVI
Virtualize CPU performance counters
Virtualize IOMMU (IO memory management unit)
OK
Cancel
Help
Primary IP address: Network information is not available



Silvereye Installer for Eucalyptus
Multi-system Install: Install Node Controllers first
Install CentOS 6 with Eucalyptus Node Controller
Install CentOS 6 with Eucalyptus Frontend
Single-system Install
Install CentOS 6 with Eucalyptus Cloud-in-a-box
Other Options
Install generic CentOS 6 without Eucalyptus
Rescue installed system
Boot from local drive
Memory test
Press [Tab] to edit options
EUCALYPTUS


Welcome to CentOS for x86_64
Disc Found
To begin testing the media before installation press OK.
Choose Skip to skip the media test and start the installation.
OK
Skip
<Tab>/<Alt-Tab> between elements | <Space> selects | <F12> next screen



What language would you like to use during the installation process?
Bulgarian (Български)
Catalan (Català)
Chinese(Simplified) (中文（简体）)
Chinese(Traditional) (中文（正體）)
Croatian (Hrvatski)
Czech (Čeština)
Danish (Dansk)
Dutch (Nederlands)
English (English)
Estonian (eesti keel)
Finnish (suomi)
French (Français)
German (Deutsch)
Greek (Ελληνικά)
Gujarati (ગુજરાતી)
Hebrew (עברית)
Hindi (हिन्दी)
Back
Next



Next Yes discard ..


Please name this computer. The hostname identifies the computer on a network.
Hostname:
localhost.localdomain
You must configure at least one network interface. For advanced configuration, use the "Configure Network" button at the bottom of the screen.
Network Interface
eth0
Mode
DHCP
IP Address
Netmask
Default Gateway
DNS server list
Advanced Network Configuration
Back
Next

Please select the nearest city in your time zone:





Selected city: Kolkata, Asia


Asia/Kolkata

☑ System clock uses UTC


Back Next



The root account is used for administering the system. Enter a password for the root user.
Root Password:
Confirm:
Back
Next



Please enter the required information
to configure your Eucalyptus Cloud.
Public IP range/list:
172.16.128.1-172.16.128.100
Below are some advanced options which you will generally not need to modify.
Public Network Interface:
eth0
Private Network Interface:
br0
Private Subnet:
172.31.254.0
Private Netmask:
255.255.254.0
Addresses per security group:
32
DNS server:
172.16.0.2
NC Bridge IP:
172.31.252.1
Below is some brief information about the configuration settings on this screen. For more detailed explanations, please see the Eucalyptus Administrators' Guide.
Public IP range - This is the range of available public IP addresses which can be mapped to instances. It should be two IPs separated by a dash (e.g. 192.168.1.100-192.168.1.20
This range should have enough IP addresses for the maximum number of instances which are intended to run concurrently in the cloud. These addresses must be on the same subnet as your public network interface, and must not be in use by other systems on the network.
Back
Next




Write changes to disk



EUCALYPTUS
Packages completed: 171 of 847
Installing libssh2-1.4.2-1.el6.x86_64 (317 KB)
A library implementing the SSH2 protocol
Back
Next



Congratulations, your Eucalyptus installation is complete.
Please reboot to use the installed system. Note that updates may be available to ensure the proper functioning of your system and installation of these updates is recommended after the reboot.
Back
Reboot



Welcome
License Information
Create User
Date and Time
Configuration Complete
Welcome
There are a few more steps to take before your system is ready to use.
The Setup Agent will now guide you through some basic configuration.
Please click the "Forward" button in the lower right corner to continue
CentOS 6
Community ENTerprise Operating System



Welcome
License Information
Create User
Date and Time
Configuration Complete
License Information
CentOS-6 EULA
CentOS-6 comes with no guarantees or warranties of any sorts, either written or implied.
The Distribution is released as GPLv2. Individual packages in the distribution come with their own licences. A copy of the GPLv2 license is included with the distribution media.
Yes, I agree to the License Agreement
No, I do not agree



Welcome
License Information
Create User
Date and Time
Configuration Complete
Create User
You must create a 'username' for regular (non-administrative) use of your system. To create a system 'username', please provide the information requested below.
Username: shagun_mishra
Full Name: Shagun Mishra
Password: •••••••
Confirm Password: •••••••
If you need to use network authentication, such as Kerberos or NIS, please click the Use Network Login button.
Use Network Login...
If you need more control when creating the user (specifying home directory, and/or UID), please click the Advanced button.
Advanced...



Welcome
License Information
Create User
Date and Time
Configuration Complete
Date and Time
Please set the date and time for the system.
Date and Time
Current date and time: Fri 11 Sep 2026 08:33:58 AM IST
Synchronize date and time over the network
Synchronize date and time on your computer with a remote time server using the Network Time Protocol:
NTP Servers
0.centos.pool.ntp.org
1.centos.pool.ntp.org
2.centos.pool.ntp.org
Add
Edit
Delete
Advanced Options



Welcome
License Information
Create User
Date and Time
Configuration Complete
Configuration Complete
Your eucalyptus installation is now complete. You may now login to the local desktop environment on this system, or you can use a web browser to connect from a remote system. Please make note of the following login credentials:
User Console URL (for managing instances, volumes, etc.):
https://172.16.128.0:8888/
User Credentials:
* Account: demo
* Username: admin
* Password: password
Admin Console URL (for managing user accounts, VM types, etc.):
https://172.16.128.0:8443
Admin Credentials:
* Account: eucalyptus
* Username: admin
* Password: admin



CentOS release 6.4 (Final)
Shagun Mishra
Other...



Applications
Places
System
Fri Sep 11, 08:36
Shagun Mishra
Change desktop appearance and behavior, get help, or log out
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash



Eucalyptus
CentOS 6
Applications Places System
Fri Sep 11, 08:38 Shagun Mishra
Untrusted Connection - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Untrusted Connection
https://172.16.128.0:8443
Google
Mozilla Firefox is free and open s
Know your rights...
Add Security Exception
You are about to override how Firefox identifies this site.
Legitimate banks, stores, and other public sites will not ask you to do this.
Server
Location: https://172.16.128.0:8443/
Get Certificate
Certificate Status
This site attempts to identify itself with invalid information.
View...
Wrong Site
Certificate belongs to a different site, which could indicate an identity theft.
Unknown Identity
Certificate is not trusted, because it hasn't been verified by a recognized authority using a secure signature.
Permanently store this exception
Confirm Security Exception
Cancel
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash



Eucalyptus - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Eucalyptus
https://172.16.128.0:8443
Google
Mozilla Firefox is free and open source software from the non-profit Mozilla Foundation.
Know your rights...
Signup Account
Reset Password
Sign in to your EUCALYPTUS cloud
Account eucalyptus
User admin
Password
Stay signed in
Sign in
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash



Applications Places System
Fri Sep 11, 08:40 Shagun Mishra
Eucalyptus - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Eucalyptus
https://172.16.128.0:8443
Google
Mozilla Firefox is free and open source software from the non-profit Mozilla Foundation.
Know your rights...
Loading...
33%
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash
Enter first time information
First time login. Please fill in the following information:
Email
tcsc@gmail.com
Old password
New password
Type again
Cancel
OK


Applications Places System
Fri Sep 11, 08:41 Shagun Mishra
Eucalyptus - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Eucalyptus
https://172.16.128.0:8443
Google
Mozilla Firefox is free and open source software from the non-profit Mozilla Foundation.
Know your rights...
EUCALYPTUS
admin@eucalyptus
QUICK LINKS
System Management
Start
Service Components
Identity Management
Accounts
Groups
Users
Policies
Keys
Certificates
Resource Management
Images
VmTypes
START GUIDE
Welcome to your Eucalyptus-Powered Cloud
Following are some quick guides to the things you can do with your cloud's Web dashboard.
MANAGE IDENTITIES AND YOUR PROFILE
View or change your personal profile details
Show all accounts under your management
Show your account's groups
Show your account's users
Show the keys you have
MANAGE CLOUD SERVICES AND RESOURCES
View and configure cloud service components


Eucalyptus
CentOS 6
Applications Places System
Fri Sep 11, 08:47 Shagun Mishra
Untrusted Connection - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Untrusted Connection
https://172.16.128.0:8888
Google
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash
This Connection is Untrusted
You have asked Firefox to connect securely to 172.16.128.0:8888, but we can't confirm that your connection is secure.
Normally, when you try to connect securely, sites will present trusted identification to prove that you are going to the right place. However, this site's identity can't be verified.
What Should I Do?
If you usually connect to this site without problems, this error could mean that someone is trying to impersonate the site, and you shouldn't continue.
Get me out of here!
Technical Details
I Understand the Risks


Applications Places System
Fri Sep 11, 08:4
Untrusted Connection - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Untrusted Connection
https://172.16.128.0:8888
Google
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash
Add Security Exception
You are about to override how Firefox identifies this site.
Legitimate banks, stores, and other public sites will not ask you to do this.
Server
Location: https://172.16.128.0:8888/
Get Certificate
Certificate Status
This site attempts to identify itself with invalid information.
View...
Wrong Site
Certificate belongs to a different site, which could indicate an identity theft.
Unknown Identity
Certificate is not trusted, because it hasn't been verified by a recognized authority using a secure signature.
Permanently store this exception
Confirm Security Exception
Cancel


Applications Places System
Fri Sep 11, 08:49 Shagun Mishra
Eucalyptus - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Eucalyptus
https://172.16.128.0:8888
Google
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash
Log in to your console
LOG IN TO EUCALYPTUS
Account name
demo
Username
admin
Password
Remember me
Forgot your password? Contact your cloud administrator.
Log in to Eucalyptus
or
LOG IN TO AWS
Access key ID
Secret access key
Remember my keys
Need to access an IAM account? Contact your cloud administrator.
Log in to AWS


Applications Places System
Fri Sep 11, 08:49 Shagun Mishra
Eucalyptus - Mozilla Firefox
File Edit View History Bookmarks Tools Help
Eucalyptus
https://172.16.128.0:8888/#dashboard
Google
Computer
shagun_mishra's Home
Eucalyptus Documentation
Eucalyptus User Console
Eucalyptus Web Admin
Trash
EUCALYPTUS
Dashboard
Images
Instances
Storage
Dashboard
Instances
In all availability zones
0
Running
0
Stopped
0
In Scaling Groups
Launch new inst
Storage
0
Volumes
0
Snapshots
Network & Security
1
Security Groups
2
Key Pairs
0
IP Addresses