Initial Dialog Map (Dynamic Model)

Prepared per Lab 2 Manual, Section 3.3 (Dynamic Model) — initial version, to be finalized in Lab 3

---

1. Overview

The Dialog Map below is a UML state machine (Fox, p.420) whose states are the application's distinct UI presentations. Five of the seven states correspond directly to the Lab 1 UI mockups (Setup, Calibration, Settings, the active-reading overlay, and the recalibration-prompt modal); two additional states — Reading with Autoscroll Disabled and Reading with Autoscroll Paused — were added because the mockups' own annotations and the Lab 1 functional requirements make them necessary (e.g. the user can deny camera access, skip calibration, or manually pause autoscrolling, each of which puts the reading view into a visibly different mode). Each transition is traceable to a specific Lab 1 use case (bracketed “[UC #]” tags) or to a mockup-level interaction. With 15 transitions among 7 states, inline text labels on the diagram collided regardless of offsetting, so each transition is instead marked with a small numbered badge on the diagram, keyed to the legend table below.




Figure 1. Doomscroll dialog map: 7 UI states and 15 numbered transitions (see legend, Table 1).

2. Transition Legend

#	From	To	Trigger / Event
1	Setup	Calibration	Allow Camera Access [UC 1.1]
2	Setup	Reading — Autoscroll Disabled	Not now / deny [UC 1.1 alt]
3	Calibration	Reading — Autoscroll Active	Calibration complete [UC 1.2]
4	Calibration	Reading — Autoscroll Disabled	Skip calibration [UC 1.2 alt]
5	Reading — Autoscroll Active	Recalibration Prompt	sustained low confidence [UC 1.3]
6	Recalibration Prompt	Calibration	Recalibrate now
7	Recalibration Prompt	Reading — Autoscroll Active	Remind me later
8	Reading — Autoscroll Active	Reading — Autoscroll Paused	pause [UC 5.2]
9	Reading — Autoscroll Paused	Reading — Autoscroll Active	resume [UC 5.2]
10	Reading — Autoscroll Active	Settings	open Settings
11	Reading — Autoscroll Paused	Settings	open Settings
12	Reading — Autoscroll Disabled	Settings	open Settings
13	Settings	Reading — Autoscroll Active	close / save [UC 5.1]
14	Settings	Calibration	Recalibrate now button
15	Reading — Autoscroll Disabled	Calibration	camera access granted later

Note: per the Lab 2 manual, this dialog map is an initial version and is expected to be refined further in Lab 3 as the design is elaborated.