



Super JumpBoo\$t Trader Manual

Hi there,

If you're reading this manual, you're already using Super JumpBoo\$t. We hope you'll find it effective and wish you a smooth and successful trading experience with the indicator.

1. Key Components of Super JumpBoo\$t

Super JumpBoo\$t consists of several key components displayed directly on the chart:

- **Trading Zones:**

The indicator highlights trading zones on the chart, categorized into 4 levels of increasing strength.

- Buy zones are indicated by 4 green levels: use these zones to look for potential buy signals.
- Sell zones are indicated by 4 pink levels: use these zones to look for potential sell signals.

- **Target Levels:** Key swing high/low points are marked to suggest potential target placements.

- **Trade Signals:**

Signals appear at each of the 4 levels, varying in strength and offering high reward potential.

- **Candle Coloring:**

- For a sell signal, candles are colored pink to indicate strong selling pressure. If the pink coloring stops, it suggests that selling momentum is weakening and a reversal may be possible.

- For a buy signal, candles are colored green to reflect strong buying pressure. When the green coloring fades, it may indicate a loss of buying strength and a possible price reversal.



3. Parameters:

Parameters	
Sensitive Mode: Enabled	☒
Offset: Level #1	1.5
Offset: Level #2	2.5
Offset: Level #3	3.5
Offset: Level #4	4.5
Offset: Base	6
Reference Price: Period	2
Line Levels Offset (Ticks)	100
Extreme: Neighborhood (Bars)	30
Signal: Close Threshold (%)	70
Signal: Quantity Per Zone	2
Signal: Split (Bars)	20


3.1. Sensitive Mode

- "Sensitive Mode":
When enabled, the indicator detects trading zones earlier, even during mild price movements—suitable for traders who prefer quicker entries.
When disabled, the indicator waits for stronger price action before displaying zones—ideal for those who prefer clearer, more confirmed signals.

3.2. Offset: Levels (#1, #2, #3, #4)

Offset: Level #1	1.5
Offset: Level #2	2.5
Offset: Level #3	3.5
Offset: Level #4	4.5

- **"Offset: Levels #1":**
This parameter sets the distance between Level #1 and the current price. Increasing the value will cause Level #1 to appear later and farther from price. Decreasing the value will make Level #1 appear sooner and closer to price.
- Similarly, **Offset: Levels #2, #3, and #4** define the distance of Levels #2, #3, and #4 from price. These values are typically set progressively higher from Level #1 to Level #4.
- In terms of support/resistance strength:
 - Level #1 is the weakest
 - Level #2 is moderate
 - Level #3 is strong
 - Level #4 is very strong
- **Note:** Avoid setting large gaps between the offset values of different levels, as this may result in uneven level distribution and could affect the consistency and reliability of signal detection.





As shown in the 2 example images above:

- In Image 1, when the offset values for all 4 levels are set higher, the levels appear farther from the current price and are plotted later.
- In Image 2, when the offset values are lowered, the levels are plotted earlier and appear closer to the price.

3.3. Offset Base


- "Offset Base": This parameter controls the frequency at which the 4-level S/R zones appear. When this value is set higher, the zones will appear less frequently. Conversely, lowering this value will cause the zones to appear more often.
- Note: Make sure the Offset Base value is set greater than or equal to "Offset: Levels #4" to ensure the indicator functions properly.

3.4. Reference Price: Period

- "Reference Price: Period" : This parameter is used to calculate the 4 S/R levels. A higher value will result in longer levels that extend across a wider range. Conversely, a lower value will produce shorter levels.

3.5. Line Levels Offset (Ticks)

- "Line Levels Offset (Ticks)": This parameter defines the minimum distance between 2 consecutive support zones (4 levels) or 2 consecutive resistance zones (4 levels). The distance is measured from Level #1 of the previous zone to Level #1 of the next adjacent zone. It helps prevent trading zones from appearing too close to each other or overlapping.



For example, as shown in the illustration above, when adjusting **Line Levels Offset (Ticks) = 100**, this means the distance between two consecutive resistance zones must be greater than or equal to 100 ticks. This distance is measured from Level #1 of one zone to Level #1 of the next zone.

3.6. Extreme Neighborhood (Bars)


- "Extreme Neighborhood (Bars) ": Define the number of bars to the left and right of a swing point. For example, if you set "Neighborhood" as 3 bars, a top must be higher than the price/plot values at 3 bars to its left and 3 bars to its right.
- Note: If you set this parameter too low, multiple support and resistance zones will be formed from the highs and lows. Conversely, setting this parameter too high will result in fewer support and resistance zones being formed from the highs and lows.

3.7. Signal: Close Threshold (%)

- "Signal: Close Threshold (%)": This parameter defines the minimum percentage of the closing price relative to the entire candle range (from Low to High) for the candle to be considered a valid signal.

For a Sell signal, the candle is considered valid if the closing price is within the top 70% of the candle range, starting from the Low.

Conversely, for a Buy signal, the closing price must be within the bottom 70% of the candle range, starting from the High.



As shown in the image above, when setting Signal: Close Threshold (%) = 70, this means that for a candle to be considered a valid Sell signal, its closing price must be positioned at least 70% of the way from the bottom (Low) to the top (High) of the candle range, meaning it should be closer to the Low of the candle.

3.8. Signal: Quantity Per Zone

- "Signal: Quantity Per Zone": This parameter defines the maximum number of trade signals that can appear within the same support or resistance zone.
- Note: It is not recommended to set this value too high, as repeated price touches of the same support or resistance zone can reduce the reliability of the signals within that zone. Limiting the number of signals per zone helps prevent "signal spamming" and keeps the trading strategy more streamlined and effective.

3.9. Signal: Split (Bars)

- "Signal Split (Bars)": This parameter defines the minimum distance (in bars) between 2 consecutive signals.

4. Suggested Settings

Settings: KingRenko\$ & ninZaRenko 12/4

Parameters	
Sensitive Mode: Enabled	☒
Offset: Level #1	1
Offset: Level #2	2
Offset: Level #3	3
Offset: Level #4	4
Offset: Base	5
Reference Price: Period	20
Line Levels Offset (Ticks)	50
Extreme: Neighborhood (Bars)	10
Signal: Close Threshold (%)	90
Signal: Quantity Per Zone	2
Signal: Split (Bars)	30

Settings: KingRenko\$ & ninZaRenko 20/5

Parameters	
Sensitive Mode: Enabled	☒
Offset: Level #1	2
Offset: Level #2	3
Offset: Level #3	4
Offset: Level #4	5
Offset: Base	8
Reference Price: Period	5
Line Levels Offset (Ticks)	100
Extreme: Neighborhood (Bars)	10
Signal: Close Threshold (%)	90
Signal: Quantity Per Zone	2
Signal: Split (Bars)	30

Settings: 100 Tick chart

Parameters	
Sensitive Mode: Enabled	☒
Offset: Level #1	1
Offset: Level #2	2
Offset: Level #3	3
Offset: Level #4	4
Offset: Base	5
Reference Price: Period	2
Line Levels Offset (Ticks)	100
Extreme: Neighborhood (Bars)	30
Signal: Close Threshold (%)	70
Signal: Quantity Per Zone	2
Signal: Split (Bars)	20

Settings: 1 Minute Chart

Parameters	
Sensitive Mode: Enabled	☒
Offset: Level #1	1
Offset: Level #2	2
Offset: Level #3	3
Offset: Level #4	4
Offset: Base	4
Reference Price: Period	5
Line Levels Offset (Ticks)	100
Extreme: Neighborhood (Bars)	30
Signal: Close Threshold (%)	80
Signal: Quantity Per Zone	2
Signal: Split (Bars)	20

5. NinjaScripts Signals

You can rely on the signals below to build your own strategy:

- ***Signal_Trade***: 1 = *bullish*, -1 = *bearish*
- ***Signal_State***: 1 = *bullish strengthening*, -1 = *bearish strengthening*

Below is the example condition for this indicator based on the **Signal_Trade**:

If Signal_Trade equal to 1, you can enter long here.

Conversely, if Signal_Trade equal to -1, you can enter short here.

Please follow the link below to find more information about Strategy Builder.

<https://youtu.be/mtMNjOQtQE>