

CSA1509-Cloud computing and Big Data Analytics

Name : M.KOUSHIK REDDY

Reg.no: 192372185

EXP 14 : Create a Virtual Hard Disk and allocate the storage using VM ware Workstation.

Aim:


To Create a Virtual Hard Disk and allocate the storage using VM ware Workstation.

Steps:


1. Download VMware software and install it as Type-2 Hypervisor.
2. Download Ubuntu or tiny os as ISO image file.
3. In VMware workstation → Create new VM
4. Do the configuration based on given conditions.
 - a. Add extra Hard disk and allocate Storage to it.
5. Created a virtual Machine.
6. Launch the VM.

Implementation:


1. Download and open VMware software.



2.Create a new VM



Name it anything→click on next→Adjust the size of disk → change the option to first and then click on next.



Click on Finish to Launch .

3.VM is created

The screenshot displays the 'Virtual Machine Settings' window for a new Ubuntu VM. On the left, the 'Devices' list includes Memory (4 GB), Processors (2), Hard Disk (SCSI) (10 GB), CD/DVD (SATA) (Auto detect), Network Adapter (NAT), USB Controller (Present), Sound Card (Auto detect), Printer (Present), and Display (Auto detect). Below this, the 'Description' section is empty. The main area shows a black rectangle representing the VM's display. At the bottom, the 'Virtual Machine Details' section shows the VM is 'Powered off', its configuration file is 'C:\Users\G POOJITHA\Documents\Virtual Machines\Ubuntu (7)\Ubuntu (7).vmx', its hardware compatibility is 'Workstation 17.x virtual machine', and its primary IP address is 'Network information is not available'.

Ubuntu (7)

Power on this virtual machine
Edit virtual machine settings

▼ Devices

Memory	4 GB
Processors	2
Hard Disk (SCSI)	10 GB
CD/DVD (SATA)	Auto detect
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

▼ Description

Type here to enter a description of this virtual machine.

▼ Virtual Machine Details

State: Powered off
Configuration file: C:\Users\G POOJITHA\Documents\Virtual Machines\Ubuntu (7)\Ubuntu (7).vmx
Hardware compatibility: Workstation 17.x virtual machine
Primary IP address: Network information is not available

4. Double-click on Hard disk and Click on add and create a new Hard disk

The screenshot shows the 'Add Hardware Wizard' dialog box in VMware Workstation. The 'Specify Disk Capacity' step is active, asking 'How large do you want this disk to be?'. The 'Maximum disk size (GB)' is set to 15.0, and the 'Recommended size for Ubuntu' is 20 GB. The 'Allocate all disk space now' checkbox is unchecked. The 'Store virtual disk as a single file' radio button is selected. The 'Split virtual disk into multiple files' option is also visible. The 'Add...' button is highlighted at the bottom of the wizard. The background shows the 'Virtual Machine Settings' window for 'Ubuntu (3)' with a list of devices including Memory (8 GB), Processors (4), Hard Disk (SCSI) (15 GB), Hard Disk 2 (SCSI) (3 GB), CD/DVD (SATA) (Using file C:\Users\yashu\OneDrive\Documents\Virtual Machines\Ubuntu (3)\Ubuntu (3).iso), Network Adapter (NAT), USB Controller (Present), Sound Card (Auto detect), Printer (Present), and Display (Auto detect).

Ubuntu (3) - VMware Workstation

File Edit View VM Tabs Help

Home x Ubuntu (3) x Clone

▼ Devices

Memory	8 GB
Processors	4
Hard Disk (SCSI)	15 GB
Hard Disk 2 (SCSI)	3 GB
CD/DVD (SATA)	Using file C:\Users\yashu\OneDrive\Documents\Virtual Machines\Ubuntu (3)\Ubuntu (3).iso
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

▼ Description

Type here to enter a description of this virtual machine.

Virtual Machine Settings

Hardware Options

Device Summary

Memory	8 GB
Processors	4
Hard Disk (SCSI)	15 GB
Hard Disk 2 (SCSI)	3 GB
CD/DVD (SATA)	Using file C:\Users\yashu\OneDrive\Documents\Virtual Machines\Ubuntu (3)\Ubuntu (3).iso
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

Disk file

C:\Users\yashu\OneDrive\Documents\Virtual Machines\Ubuntu (3)\Ubuntu (3).iso

Capacity

Current size: 448 KB

Add Hardware Wizard

Specify Disk Capacity

How large do you want this disk to be?

Maximum disk size (GB): 15.0

Recommended size for Ubuntu: 20 GB

☐ Allocate all disk space now.

Allocating the full capacity can enhance performance but requires all of the physical disk space to be available right now. If you do not allocate all the space now, the virtual disk starts small and grows as you add data to it.

☒ Store virtual disk as a single file

☐ Split virtual disk into multiple files

Splitting the disk makes it easier to move the virtual machine to another computer but may reduce performance with very large disks.

< Back Next > Cancel

Add... Remove

OK Cancel Help

Defragment Expand... Compact Advanced...

36°C Partly sunny

Search

ENG US

13:58 30-07-2026

6. VM is created according to the conditions given.

