

KAFR ELSHEIKH UNIVERSITY
FACULTY OF SCIENCE
DEPARTMENT OF PETROLEUM GEOLOGY AND
MINERAL EXPLORATION
SECOND LEVEL

METHODS OF RADIOACTIVE ORES EXPLORATION

PREPARED BY :

*YOUSEF ELGNDY ELMAHDY
*AHMED ALI BASIONY
*ALI MOHAMED ALI
*AHMED MAHMOUD MOHAMED
*SHEHAB TAREK
*FARES MAHER KHAMIS
*AL-BARAA ABD EL-SATAR
*MOHMED HANY

Introduction:

Radioactive ores, particularly those containing uranium and thorium, represent highly valuable mineral resources due to their wide range of applications in nuclear energy production, medical treatments, scientific research, and defense industries. The exploration of such ores is a complex and multidisciplinary process that relies on the integration of several geological and geophysical techniques to locate economically viable deposits.

Unlike conventional metallic ores, radioactive minerals possess a distinct advantage in exploration, as they emit detectable radiation. This property allows geologists to identify potential mineralization zones more efficiently. Typically, the exploration process begins with the collection and analysis of existing geological data, followed by field investigations, geophysical and geochemical surveys, and ultimately drilling operations. No single method is sufficient on its own; therefore, multiple techniques must be integrated to ensure accurate and reliable results.

1. Geological Methods

Geological methods form the foundation of radioactive ore exploration. These methods are based on the understanding that radioactive minerals occur within specific rock types and geological environments.

Geologists initially examine geological maps, previous research, and satellite imagery to identify areas that may host uranium or thorium deposits. Favorable environments include granitic rocks, sandstone formations, unconformity zones, metamorphic rocks, pegmatites, and hydrothermal vein systems.

Uranium mineralization is commonly associated with granitic rocks, which may contain radioactive minerals such as uraninite, pitchblende, and monazite. Sandstone-hosted uranium deposits are also significant, as uranium can be transported by groundwater and concentrated in porous formations.

Field mapping is then conducted to gather detailed information about the study area.

Geologists record rock types, geological age, structural features, fractures, faults, and any evidence of alteration or mineralization. Structural elements, particularly faults and fractures, are important because they can act as pathways for mineral-bearing fluids.

Alteration zones are also carefully examined, as hydrothermal fluids often modify the

surrounding rocks. Common alteration processes include hematization, silicification, chloritization, and kaolinization. These features may indicate previous movement of uranium-bearing fluids.

In most exploration programs, geological investigations help reduce large regions into smaller, more promising target areas before applying more advanced techniques.

2. Radiometric Methods

Radiometric methods are among the most important techniques used in radioactive ore exploration because radioactive elements naturally emit radiation.

These methods primarily measure gamma rays emitted by uranium, thorium, and potassium. Variations in radiation intensity allow geologists to identify anomalous zones that may indicate the presence of radioactive minerals. Radiometric surveys are commonly divided into two types:

A. Ground Radiometric Survey

In ground surveys, geologists use portable instruments such as Geiger-Müller counters, scintillation counters, and gamma-ray spectrometers to measure radiation directly at the surface.

Areas that exhibit higher radiation levels compared to their surroundings are referred to

as anomalies. These anomalies may suggest the presence of radioactive mineralization beneath the surface. Ground surveys are highly accurate; however, they can be time consuming and costly when applied over large areas.

B. Airborne Radiometric Survey

Airborne surveys involve mounting radiation detectors on aircraft, helicopters, or drones.

The survey is conducted by flying along parallel lines while continuously recording radiation levels.

This method allows for rapid coverage of large and remote areas, reduces exploration

costs, and facilitates efficient mapping of radiation anomalies. However, airborne

surveys are generally less precise than ground surveys due to the attenuation of

radiation with increasing distance from the ground.

Airborne surveys are typically used in the early stages of exploration, while ground

surveys are employed later to verify and refine the results.

3. Magnetic Surveys

Although uranium itself is not magnetic, many radioactive deposits are associated with

magnetic rocks or geological structures. For this reason, magnetic methods are often

used in conjunction with radiometric surveys. Magnetic surveys measure variations in the Earth's magnetic field caused by differences in subsurface rock properties. These surveys are useful for identifying faults, fractures, igneous intrusions, basement structures, and potential structural traps. For example, if uranium mineralization is related to a granite intrusion, magnetic data can help define the extent and geometry of that intrusion. Magnetic surveys may be conducted on the ground, from aircraft, or using drones. While magnetic methods do not directly detect uranium, they provide valuable information about the geological framework of the area.

4. Electrical and Electromagnetic Methods

Electrical methods are used because rocks containing radioactive minerals often exhibit different electrical properties compared to surrounding rocks. Common techniques include resistivity, induced polarization (IP), and electromagnetic (EM) methods. The resistivity method measures the ability of rocks to resist electrical current flow. Some mineralized zones may show low resistivity due to the presence of water, clay, or sulfide minerals, while others may exhibit high resistivity depending on the host rock type. Induced polarization is particularly useful when uranium is associated with sulfide

minerals. This method measures the ability of rocks to temporarily store electrical

charge after the current is switched off. Strong IP responses may indicate mineralized

zones.

Electromagnetic methods utilize artificial electromagnetic fields to investigate

subsurface conditions. They are effective in detecting conductive faults, fractured

zones, water-bearing formations, and buried ore bodies.

These methods are typically applied after identifying radiometric anomalies to better

understand the depth and extent of mineralization.

5. Geochemical Methods

Geochemical exploration involves collecting and analyzing environmental samples to

detect traces of uranium or thorium.

Samples may include soil, rocks, stream sediments, groundwater, surface water, and

vegetation. Because uranium can dissolve and be transported by water under certain

conditions, water and sediment samples are particularly useful.

Soil sampling is conducted using a grid pattern, where samples are collected at regular

intervals and analyzed in laboratories. Areas showing elevated uranium concentrations

may indicate underlying mineralization.

Water sampling is also important, as elevated uranium levels in rivers, lakes, or

groundwater may suggest nearby or upstream sources. In addition, geologists often use pathfinder elements such as vanadium, molybdenum, selenium, copper, lead, and zinc, which are commonly associated with uranium deposits. Radon gas, a product of uranium decay, is another important indicator. High radon concentrations in soil gas may suggest the presence of radioactive minerals below the surface. Geochemical methods are particularly valuable for detecting concealed deposits that lack visible surface expression.

6. Remote Sensing and Satellite Imagery

Remote sensing has become an essential tool in modern mineral exploration, allowing geologists to investigate large regions efficiently without extensive fieldwork. This approach utilizes satellite imagery, aerial photography, and drone-based imaging to analyze surface features. These data help identify rock types, structural features such as faults and fractures, alteration zones, drainage patterns, and variations in surface color. Certain alteration minerals associated with radioactive deposits, particularly iron oxides, can be recognized through their spectral signatures, often appearing as reddish or

orange zones.

Two important remote sensing techniques include multispectral imaging and hyperspectral imaging. Multispectral imaging captures data across several wavelength

bands and is useful for identifying general geological features.

Hyperspectral imaging,

on the other hand, records hundreds of wavelength bands and allows for precise mineral

identification.

Remote sensing significantly reduces exploration time and cost by narrowing down

potential target areas before detailed field investigations are conducted.

7. Drilling and Borehole Investigation

Once a promising target has been identified, drilling is carried out to confirm the

presence of radioactive ore beneath the surface. Drilling represents the final and most

expensive stage of the exploration process.

Common drilling methods include core drilling, rotary drilling, and reverse circulation

drilling.

Core drilling is particularly important because it produces cylindrical rock samples

known as cores. These samples provide detailed information about rock type, mineral

content, thickness of the ore zone, grade of mineralization, and structural features.

After drilling, borehole logging is conducted using specialized instruments lowered into

the drill hole. Gamma logging is especially significant, as it measures natural radioactivity along the borehole. This process allows geologists to determine the exact depth, thickness, and distribution of uranium within the deposit. Drilling is the only method capable of confirming whether a deposit is economically viable.

8. Reserve Estimation

If drilling confirms the presence of radioactive mineralization, the next step is reserve estimation. This process involves calculating the total quantity of ore, average grade, and overall economic value of the deposit. Geologists use drilling data, laboratory analyses, and computer modeling techniques to estimate the size and geometry of the ore body. A deposit is considered economically viable only if the uranium concentration is sufficiently high, the deposit is large enough, extraction costs are reasonable, and transportation and processing are feasible. Reserve estimation is a critical stage that determines whether mining operations can proceed.

9. Environmental and Safety Considerations

The exploration of radioactive ores requires strict adherence to environmental and safety regulations due to the potential hazards associated with radiation exposure.

Key safety measures include the use of protective equipment, continuous monitoring of radiation levels, limiting exposure time, proper handling of samples, and safe disposal of contaminated materials.

In addition, exploration activities must consider potential environmental impacts,

including water contamination, soil disturbance, dust generation, and damage to vegetation.

Environmental impact assessments are typically required before drilling or mining

activities begin. Ensuring safe and responsible exploration practices is essential for

protecting both workers and the environment.

10. Conclusion

The exploration of radioactive ores is a complex and highly specialized process that

depends on the integration of multiple scientific methods. Geological studies identify

favorable environments, radiometric surveys detect anomalies, geochemical techniques

reveal hidden mineralization, and drilling confirms the presence of ore deposits.

No single method is sufficient on its own; the most reliable results are achieved through the combined application of all techniques in a systematic manner. Advances in modern technology, particularly in remote sensing and geophysical instrumentation, have significantly improved the efficiency, accuracy, and cost-effectiveness of radioactive ore exploration.

References

- Moon, C. J., Whateley, M. K. G., & Evans, A. M. (2006). Introduction to Mineral Exploration (2nd ed.). Blackwell Publishing.
- Hartman, H. L., & Mutmansky, J. M. (2002). Introductory Mining Engineering (2nd ed.). Wiley.
- Telford, W. M., Geldart, L. P., & Sheriff, R. E. (1990). Applied Geophysics (2nd ed.). Cambridge University Press.
- Lillesand, T., Kiefer, R. W., & Chipman, J. (2015). Remote Sensing and Image Interpretation (7th ed.). Wiley.
- International Atomic Energy Agency (IAEA). (2018). Guidebook on the Exploration for Uranium Deposits.
- World Nuclear Association. (2023). Uranium Exploration Methods.
- United States Geological Survey (USGS). (2022). Uranium and Thorium Resources Data.

