

Getting Started

Quickstart Guide

What is ZeroTier?

OS and Device Compatibility

Awesome ZeroTier Things

This is ZeroTier

Guides

OS / Platform Notes

FAQ & Troubleshooting

Glossary

Quickstart Guide

Connect two devices and ping your first server in under 5 minutes.

1. Create Network

1. Visit [my.zerotier.com](#) in your web browser and log in
2. Click the **Create A Network** button
3. **Copy the Network ID** - this is a 16-character code like `d5e04297a16fa690`

Keep this browser tab open - you'll need it in step 4.

2. Install ZeroTier and Join Your Network

Visit our [downloads page](#) and install ZeroTier on each device that will connect to this network.

3. Join Your Network

On PC/MacOS

1. Locate the ZeroTier icon in your menu bar (if MacOS) or system tray (if Windows)
2. Click the icon -> **Join New Network...**
3. Paste your Network ID and click **Join**

Using CLI

ZeroTier's command line interface (CLI) works on any device with an accessible terminal.

```
sudo zerotier-cli join NETWORK_ID
```

4. Authorize Your Devices

1. Go back to your browser tab with [my.zerotier.com](#) and click on your network
2. Scroll down to the **Members** section - you should see your devices connected from the step above
3. For each device, toggle the left checkbox. Then, click **Authorize**

*Your devices should now show a green checkbox under the **Auth** column*

5. Test Your Connection

Find Your IP Addresses

In the **Members** section on the website, note the **Managed IP** addresses (like `192.168.191.242`)

Test the Connection

Type this command in any terminal, replacing `MANAGED_IP` with one of your device's IP addresses (be sure to ping a device separate from the one you are using!):

```
ping -n 3 MANAGED_IP
```

Success looks like this:

```
PING 10.147.17.101 (10.147.17.101): 56 data bytes
64 bytes from 10.147.17.101: icmp_seq=0 ttl=64 time=15.2 ms
64 bytes from 10.147.17.101: icmp_seq=1 ttl=64 time=12.1 ms
64 bytes from 10.147.17.101: icmp_seq=2 ttl=64 time=11.8 ms
```

You did it! Your devices are now securely connected.

Leaving a Network

When you no longer need to be connected to a network, you can leave it:

- Click the ZeroTier icon in your menu bar/system tray
- Click the network name to uncheck it (or use **Network Details** to uncheck the Connected checkbox)
- To permanently remove a network, use **Network Details** -> **Delete Network**

Alternatively, use the CLI command:

```
sudo zerotier-cli leave NETWORK_ID
```

Next Steps

- [SSH and Remote Desktop](#)
- [Network File Sharing](#)
- [Host a website across your network](#)

Tags: [tutorial](#) [newcomer](#) [installation](#) [client](#) [central](#) [admin](#)

1. Create Network
2. Install ZeroTier and Join Your Network
3. Join Your Network

On PC/MacOS

Using CLI
4. Authorize Your Devices
5. Test Your Connection

Find Your IP Addresses

Test the Connection
- Leaving a Network
- Next Steps

Product

- Download [↗](#)
- ZeroTier Central [↗](#)
- Pricing
- Security

Documentation

- Getting Started
- This is ZeroTier
- Guides
- FAQ

Community & Support

- Discussion Forum [↗](#)
- GitHub [↗](#)
- Contact Support [↗](#)

Company

- About [↗](#)
- Blog [↗](#)
- Careers [↗](#)
- Privacy Policy [↗](#)