exit reason	dmesg	ept=0	ept=0 NOT set
all types	, all exits, exits=	2292304	695480
* exit # 48 : EPT violation	. exit # 48 exits=	0	365434
* exit # 30 : I/O instruction	, exit # 30 exits=	175583	195973
* exit # 10 : CPUID	, exit # 10 exits=	97495	90010
* exit # 28 : Control-register accesses	, exit # 28 exits=	1640347	14737
* exit # 1 : External interrupt	, exit # 1 exits=	6159	7415
* exit # 49 : EPT misconfiguration	, exit # 49 exits=	0	6986
* exit # 0 : Exception or non-maskable interrupt (NMI)	, exit # 0 exits=	252436	6741
* exit # 32 : WRMSR	, exit # 32 exits=	11490	5762
* exit # 12 : HLT	, exit # 12 exits=	444	2264
* exit # 7 : Interrupt window	, exit # 7 exits=	6503	935
* exit # 31 : RDMSR	, exit # 31 exits=	239	283
* exit # 40 : PAUSE	, exit # 40 exits=	24	30
* exit # 54 : WBINVD or WBNOINVD	, exit # 54 exits=	6	6
* exit # 55 : XSETBV	, exit # 55 exits=	2	2
* exit # 29 : MOV DR	, exit # 29 exits=	1	1
* exit # 14 : INVLPG	, exit # 14 exits=	98810	0
* exit # 58 : INVPCID	, exit # 58 exits=	26815	0
* exit # 33 : VM-entry failure due to invalid guest state	, exit # 33 exits=	12314	0
* exit # 9 : Task switch	, exit # 9 exits=	0	0
* exit # 8 : NMI window	, exit # 8 exits=	0	0
* exit # 68 : TPAUSE	, exit # 68 exits=	0	0
* exit # 67 : UMWAIT	, exit # 67 exits=	0	0
* exit # 64 : XRSTORS	, exit # 64 exits=	0	0
* exit # 63 : XSAVES	, exit # 63 exits=	0	0
* exit # 62 : Page-modification log full	, exit # 62 exits=	0	0
* exit # 61 : RDSEED	, exit # 61 exits=	0	0
* exit # 60 : ENCLS	, exit # 60 exits=	0	0
* exit # 59 : VMFUNC	, exit # 59 exits=	0	0
* exit # 57 : RDRAND	, exit # 57 exits=	0	0
* exit # 56 : APIC write	, exit # 56 exits=	0	0
* exit # 53 : INVVPID	, exit # 53 exits=	0	0
* exit # 52 : VMX-preemption timer expired	, exit # 52 exits=	0	0
* exit # 51 : RDTSCP	, exit # 51 exits=	0	0
* exit # 50 : INVEPT	, exit # 50 exits=	0	0
* exit # 47 : Access to LDTR or TR	, exit # 47 exits=	0	0
* exit # 46 : Access to GDTR or IDTR	, exit # 46 exits=	0	0
* exit # 45 : Virtualized EOI	, exit # 45 exits=	0	0
* exit # 44 : APIC access	, exit # 44 exits=	0	0
* exit # 43 : TPR below threshold	, exit # 43 exits=	0	0
* exit # 41 : VM-entry failure due to machine-check ev	e, exit # 41 exits=	0	ļ
* exit # 39 : MONITOR	, exit # 39 exits=	0	0
* exit # 37 : Monitor trap flag	, exit # 37 exits=	0	
* exit # 36 : MWAIT	, exit # 36 exits=	0	
* exit # 34 : VM-entry failure due to MSR loading	, exit # 34 exits=	0	L
* exit # 3 : INIT signal	, exit # 3 exits=	0	0
* exit # 27 : VMXON	, exit # 27 exits=	0	0
* exit # 26 : VMXOFF	, exit # 26 exits=	0	
* exit # 25 : VMWRITE	, exit # 25 exits=	0	0
* exit # 24 : VMRESUME	, exit # 24 exits=	0	
* exit # 23 : VMREAD	, exit # 23 exits=	0	0
* exit # 22 : VMPTRST	, exit # 22 exits=	0	
* exit # 21 : VMPTRLD	, exit # 21 exits=	0	0
* exit # 20 : VMLAUNCH	, exit # 20 exits=	0	
* exit # 2 : Triple fault	, exit # 2 exits=	0	0
* exit # 19 : VMCLEAR	, exit # 19 exits=	0	
* exit # 18 : VMCALL	, exit # 18 exits=	0	0
* exit # 16 : RDTSC	, exit # 16 exits=	0	
* exit # 15 : RDPMC	, exit # 15 exits=	0	
* exit # 13 : INVD	, exit # 13 exits=	0	0