

ZYVORAI LABS · CUSTOMER DOCUMENTATION

Chimera

Page-by-Page Product Manual

2026-08-29

Page-by-page guides

Each guide follows: Purpose → When to use it → How to get there → Operate from the console (UX) → Related pages.

Every route is also listed in the [complete page index](#).

Command Center

Page	What it covers
Fault Studio	Operator drawer for latency, status codes, next-N API/NFC failures, stream drops, drop offset, and bandwidth caps.
Live requests	Stream recent infrastructure HTTP calls: method, path, status, duration.
Login	Authenticate the browser session before any Command Center chrome or data is shown.
Overview KPIs	Show live gateway-derived health: requests, error rate, sessions, bytes, exports, latency.
Scenario Launcher	One-click deterministic presets for clean, slow, flaky, and resume export paths.
Settings	Show listen address and change Command Center admin username/password live (no restart).
Topology	Visual datacenter → cluster → host → datastore map of the simulated estate.
VM inventory	Searchable, paginated table of simulator VMs with power state, CPU/memory/disk, datastore, and Fixture badge.
VMDK Library	List and manage <code>.vmdk</code> fixtures under configured fixture directories; upload or browse; optionally pin to a VM.

9 guides. Regenerate: `node scripts/customer-docs/generate-guide-index.mjs` .

Fault Studio

Purpose

Operator drawer for latency, status codes, next-N API/NFC failures, stream drops, drop offset, and bandwidth caps.

When to use it

Hardening clients (Transiva) against partial transfers and API errors.

How to get there

Top bar gear, sidebar, or scenario panel → Fault Studio drawer.

What you can do

- Arm next-N failures or one-shot NFC stream drops
- Cap bandwidth; clear faults before clean runs

Related

[Scenarios](#) · [Live requests](#)

Live requests

Purpose

Stream recent infrastructure HTTP calls: method, path, status, duration.

When to use it

Debug govmomi / Transiva traffic and spot red status codes.

How to get there

Overview — Live requests panel. Top bar bell scrolls here.

What you can do

- Toggle **View All** / **View Less** (10 vs 30 buffered rows)
- Correlate failures with Fault Studio settings

Related

[Fault Studio](#) · [Overview KPIs](#)

Login

Purpose

Authenticate the browser session before any Command Center chrome or data is shown.

When to use it

Every new browser session. Mutating controls require login.

How to get there

Open `http(s)://<host>:8989/__chimera/` . Unauthenticated users see only the login page.

What you can do

- Sign in with username/password (default `admin` / `admin`)
- After login, the full overview loads

Related

[Settings](#) · [Admin basics](#)

Overview KPIs

Purpose

Show live gateway-derived health: requests, error rate, sessions, bytes, exports, latency.

When to use it

First screen after login; confirm the engine is receiving infrastructure traffic.

How to get there

Command Center home — top metrics row.

What you can do

- Refresh the window
- Note that `/__chimera` polling itself is excluded from counters

Related

[Live requests](#) · [Topology](#)

Scenario Launcher

Purpose

One-click deterministic presets for clean, slow, flaky, and resume export paths.

When to use it

Repeatable Transiva / client tests without hand-tuning Fault Studio each time.

How to get there

Overview — scenario cards.

What you can do

- **Clean Environment** — baseline happy path
- **Slow Fabric** — latency pressure
- **Flaky API** — intermittent failures
- **Resume Export** — NFC drop for Range/206 retry

Related

[Fault Studio](#) · [Workflows](#)

Settings

Purpose

Show listen address and change Command Center admin username/password live (no restart).

When to use it

After first login in any shared lab; before exposing Chimera beyond localhost.

How to get there

Dashboard Settings panel (operator chrome).

What you can do

- Review listen / endpoint info
- Rotate admin credentials used by the UI login gate

Related

[Login](#) · [Admin basics](#)

Topology

Purpose

Visual datacenter → cluster → host → datastore map of the simulated estate.

When to use it

Orient operators to inventory shape before export tests.

How to get there

Overview board — topology panel. Use **View Full Topology** for full-viewport zoom (`Fit` / `+`).

What you can do

- Inspect labels hydrated from config counts and fixture size
- Dismiss overlay via button, outside click, or Escape

Related

[VM inventory](#) · [Admin basics](#)

VM inventory

Purpose

Searchable, paginated table of simulator VMs with power state, CPU/memory/disk, datastore, and Fixture badge.

When to use it

Pick an export target; confirm fixture matching (real VMDK vs synthetic).

How to get there

Overview — VM inventory table.

What you can do

- Filter by name and power state
- Copy/select a VM for export workflows
- Hover Fixture badge for filename (`Matched` , `Round-robin` , `Shared` , `Manual` , `Synthetic`)

Related

[VMDK Library](#) · [Workflows](#)

VMDK Library

Purpose

List and manage `.vmdk` fixtures under configured fixture directories; upload or browse; optionally pin to a VM.

When to use it

Testing Transiva **conversion** with real disks, not only NFC transfer of synthetic fixtures.

How to get there

Overview — VMDK Library card.

What you can do

- Upload a `.vmdk` into `fixture_vmdk_dir`
- Browse staged host files under fixture roots only
- Pin/clear Manual assignment (overrides name/round-robin matching)
- Auto re-scan every ~5 seconds

Related

[VM inventory](#) · product-repo `docs/TRANSIVA.md`

Chimera — Complete page index

Every primary navigable dashboard route.

Generated: 2026-08-29 · 0 routes

Regenerate: `node scripts/customer-docs/generate-page-index.mjs`

Related

- [Customer docs home](#)
- [Page-by-page guides](#)