



Table Of Contents

- Building the Client Library
- Running the Client Examples
- Configuring Logging

Building the Client Library

To build the C++ Client library, please follow the instructions in `GRIDGAIN_HOME/examples/clients/cpp/readme.md` file.

Running the Client Examples

After you have built the C++ client library and installed it in your system, you can build the examples by going into the `GRIDGAIN_HOME/examples/clients/cpp` directory and executing the following commands:

```
./configure  
make
```

On Windows you can use the provided Visual Studio solution (in the `vsproject/` directory) to compile the examples code. Please note that you will have to adjust include and library directories in relevant projects to match your environment configuration.

Before you can run the examples, you must ensure that the `org.gridgain.examples.client` package are available on the GridGain node's classpath. One way to achieve that is to build the jar containing the examples code and drop it to the `GRIDGAIN_HOME/libs` directory. You can build `gridgain-examples.jar` by running `mvn package` in `GRIDGAIN_HOME/examples` folder. After that @code `gridgain-examples.jar` will be generated by Maven in `GRIDGAIN_HOME/examples/target` folder. When the `ggstart` script runs it automatically picks up the jars from that directory.

Now you can start a GridGain node as follows:

```
$GRIDGAIN_HOME/bin/ggstart.{sh,bat} examples/config/example-cache.xml
```

Alternatively you can run an instance of `ClientExampleNodeStartup` or

`ClientCacheExampleNodeStartup` Java class, which will start up a GridGain node with proper configuration. You can do this from your favourite IDE.

Once the GridGain node is up and running you can run the examples:

```
./gridgain-compute-example  
./gridgain-data-example
```

If you just compiled the client library make sure that you ran `ldconfig` to update library cache before running the example.

You can also start multiple nodes.

Feel free to modify the example source code to change communication protocol from TCP (default) to HTTP, use multiple hosts and try other options.

Configuring Logging

You can control the client's log level by setting the `GRIDGAIN_CPP_CLIENT_LOG_LEVEL` environment variable to one of the following values:

1. (error),
2. (warning),
3. (info), and
4. (debug).

By default, the log level is 3. The client sends all its log messages to stdout.