



## How to use DarkNetSpace (Windows)

DarkNetSpace Team

<http://www.darknetspace.org>

support#darknetspace.org

DarkNetSpace is a platform for anonymous application, it offers decentralized exchange based on strong anonymity technology. DarkNetCoin(DNC) is the general currency in DarkNetSpace.

DarknetCoin aims at becoming the popular currency of the DarkNet.

### Simple usage:

(1) Download DarkNetSpace,

[http://www.darknetspace.org/files/DarkNetSpace\\_Win32.zip](http://www.darknetspace.org/files/DarkNetSpace_Win32.zip)

[http://www.darknetspace.org/files/DarkNetSpace\\_Win64.zip](http://www.darknetspace.org/files/DarkNetSpace_Win64.zip)

[http://www.darknetspace.org/files/DarkNetSpace\\_Ubunbu64.zip](http://www.darknetspace.org/files/DarkNetSpace_Ubunbu64.zip)

and extract DarkNetSpace to a directory like D:\DarkNetSpace

(2) Double click to run dnsd.exe, dnsd will begin to download blockchain. Don't close it, leave it alone.

(3) Open command console, change your current directory to D:\DarkNetSpace.

Then type "simplewallet --generate-new-wallet mywallet.dat --password 12345"  
to create a new wallet.

```
cmd - simplewallet --generate-new-wallet darknetcoin --password 12345

D:\cnn\Darknetspace\dns_test>simplewallet --generate-new-wallet darknetcoin --password 12345
darknetspace wallet v0.6.5.10<0.1-g40b89f0>
Generated new wallet: D6src0Y4mTgNAWPQ3XAPPHM1issJmdMaBdzQxPDyakUNYUC7b9i75ZzPmfDAP5FnjMUgZQ9dwpZYqb4X7o9FCqvHJAzDTFw
view key: 696571b10efeea78550b25b8cacabfdc381bd6de5ec897abe55455c652840b06
*****
Your wallet has been generated.
To start synchronizing with the daemon use "refresh" command.
Use "help" command to see the list of available commands.
Always use "exit" command when closing simplewallet to save
current session's state. Otherwise, you will possibly need to synchronize
your wallet again. Your wallet key is NOT under risk anyway.
*****
[darknetspace wallet D6src0l:
```

If you want to open your wallet again, open command console, change your current directory to D:\DarkNetSpace.

Then type "simplewallet --wallet-file mywallet.dat --password 12345"

```
管理员: C:\Windows\system32\cmd.exe - simplewallet --wallet-file darknetcoin --password 12345

D:\cnn\DarknetSpace\_build\src\Release>simplewallet --wallet-file darknetcoin --password 12345
darknetspace wallet v0.6.5.10<0.1-g40b89f0>
Opened wallet: D7vLX3XdXXkDB8cAa8nETf9NHkCmir6YXXP7pkSAT9v4oGRyjMuXSVZaSGnNisfo
gJTMbUa7ESavQAEDgvSFNBWN63e7xp
Starting refresh...
Refresh done, blocks received: 19380
balance: 0.000000000000, unlocked balance: 0.000000000000
*****
Use "help" command to see the list of available commands.
*****
[darknetspace wallet D7vLX3l:
```

If you want to transfer some money to someone, then type: “ transfer 1 D4hdYVBDqSp7JNUXuf8myuAMrgGJ9Rj8KjPbdZpDN7exPDYtaNswQjH9UdHPxrBwYRXRENQysBb6ALY uwzwziZdgF7wnMdH 10 “

Or you can use wallet aliases: transfer 1 @darknetspace 10

Change the address above to your target, and change 10 to the amount being transferred.

```
cmd - simplewallet --wallet-file mineraddress --password 12345
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]:
[darknetspace wallet D4hdYU]: transfer 1 @darknet 10
Money successfully sent, transaction <738ea99dd1eaa65224a2bf0045a3746f3bf42a941
8dfa6149694212fa0147d9>, 371 bytes
[darknetspace wallet D4hdYU]: transfer 1 D4hdYUVDqSp7JNUXuf8myuAMrgGJ9Rj8KjPbdZp
DN7exPDYtaNswQjH9UdHPxrBwYRXRENQysBb6ALYuwzwwziZdgF7wnMdH 10
Money successfully sent, transaction <8fcf3ffdc58dc68826504eddc8774419938abc4b7
047b66f56b20ab32ad6a4a>, 371 bytes
[darknetspace wallet D4hdYU]:
```

(4) Mining: three methods.

A: On simplewallet command console, type: "start\_mining" to solo cpu mining, your dnsc command console will begin to mine.

B: Download minerd and run minerd\_cpu.bat to pool cpu mining(don't forget to change the miner address).

<http://www.darknetspace.org/files/cpuminer-multi-opencl-x64.zip>

C: Download minerd and run minerd\_gpu.bat to pool gpu mining, don't forget to change the miner address. BTW, you should have at least one display adapter like 7950) first .

<http://www.darknetspace.org/files/cpuminer-multi-opencl-x64.zip>

## Donation:

BTC: 1686fd9JhPfTHwRtLz4GWPUKLfEifuh2m7

DNC: @darknetspace

DB71SSN71WSWzw9GyZFTReHCde5ga94HUad9iaS5Nme5PzGsZdyvdx62T3oA

GG2PhrMRB5mkTZ93nCN mVgW58xT82cwbdXn