

Bluetooth

#### IP Configuration

☐ DHCP

☒ Static

IPv4 Address

192.168.0.1

Subnet Mask

255.255.255.0

#### IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

Link Local Address: FE80::205:5EFF:FEA4:C0A1

ADAL

tings

n Settings

**RFACE**

hernet0

etooth

#### Port Status

☒ On

#### Bandwidth

☒ 100 Mbps ☐ 10 Mbps ☒ Auto

#### Duplex

☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address

00D0.BC83.E696

#### IP Configuration

☐ DHCP

☒ Static

IPv4 Address

192.168.0.2

Subnet Mask

255.255.255.0

#### IPv6 Configuration

☐ Automatic

☒ Static

IPv6 Address

Link Local Address: FE80::2D0:BCFF:FE83:E696

Router0

Physical

Config

CLI

Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

FastEthernet0/0

Port Status

Bandwidth

Duplex

MAC Address

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

☐ On
 

☒ 100 Mbps
 ☐ 10 Mbps
 ☒ Auto

☒ Half Duplex
 ☐ Full Duplex
 ☒ Auto

0001.C7C7.9401

192.168.0.100

255.255.255.0

10

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

FastEthernet0/1

Port Status

Bandwidth

Duplex

MAC Address

IP Configuration

IPv4 Address

Subnet Mask

Tx Ring Limit

☐ On
 

☐ 100 Mbps
 ☐ 10 Mbps
 ☒ Auto

☒ Half Duplex
 ☐ Full Duplex
 ☒ Auto

0001.C7C7.9402

100.10.10.1

255.0.0.0

10

```

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 192.168.0.100 255.255.255.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#ip address 100.10.10.1 255.0.0.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#ip route 0.0.0.0 0.0.0.0 100.10.10.2
Router(config)#int fa0/0
Router(config-if)#ip nat inside
Router(config-if)#int fa0/1
Router(config-if)#ip nat inside
Router(config-if)#ip nat outside
Router(config-if)#exit
Router(config)#ip nat inside source static 192.168.0.1 100.10.11.1
Router(config)#ip nat inside source static 192.168.0.1 100.10.11.2
Router(config)#

```

Copy

```
C:\>ping 100.10.10.2
```

```
Pinging 100.10.10.2 with 32 bytes of data:
```

```
Reply from 192.168.0.100: Destination host unreachable.
```

```
Reply from 192.168.0.100: Destination host unreachable.
```

```
Reply from 192.168.0.100: Destination host unreachable.
```

```
Reply from 192.168.0.100: Destination host unreachable.
```

```
Ping statistics for 100.10.10.2:
```

```
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

```
C:\>
```