



**EDUCACIÓN**  
SECRETARÍA DE EDUCACIÓN PÚBLICA



TECNOLÓGICO  
NACIONAL DE MÉXICO®

Instituto Tecnológico de Pabellón de Arteaga

NOMBRE DE LA MATERIA  
Fundamento de Redes

NOMBRE DEL DOCENTE  
Rafael Preciado Gutiérrez

NOMBRE DEL TRABAJO  
Cubo

NOMBRE DEL ALUMNO  
Alejandro Guevara de Luna

UNIDAD

FECHA Y LUGAR  
18 de noviembre del 2022




Carretera a la Estación de Rincón Km 1, C.P. 20670 Pabellón de  
Arteaga, Aguascalientes  
tecnm.mx | pabellon.tecnm.mx



2022 *Ricardo*  
*Flores*  
Año de *Magón*  
PRECURSOR DE LA REVOLUCIÓN MEXICANA



Instituto Tecnológico de Pabellón de Arteaga





Router Principal

Physical

Config

CLI

Attributes

IOS Command Line Interface

Press RETURN to get started.

Router>enable  
Router#config t  
Enter configuration commands, one per line. End with CNTL/Z.  
Router(config)#interface fa 0/0  
Router(config-if)#ip address 192.168.12.1  
% Incomplete command.  
Router(config-if)#ip address 192.168.12.1 255.255.255.0  
Router(config-if)#no shutdown  
  
Router(config-if)#  
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up  
  
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up  
  
Router(config-if)#exit  
Router(config)#interface s 0/0/0  
Router(config-if)#ip address

Copy

Paste

☐ Top





Router1

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
Processor board ID FTX0947218E
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.13.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy

Paste

☐ Top





Router2

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Processor board ID F1A09472102
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.14.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy

Paste

☐ Top





Router3

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.14.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#ip address 192.168.15.1 255.255.255.0
Router(config-if)#
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#
```

Copy

Paste

☐ Top





Router4

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Processor board ID FTX0947218E
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.16.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy

Paste

☐ Top







Router5

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
Processor board ID FTX0947Z18E
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.17.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy

Paste

☐ Top







Router6

Physical Config **CLI** Attributes

IOS Command Line Interface

```
Processor board ID FTX0947218E
M860 processor: part number 0, mask 49
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.18.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy Paste

☐ Top





Router7

Physical Config CLI Attributes

IOS Command Line Interface

```
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

--- System Configuration Dialog ---

Would you like to enter the initial configuration dialog? [yes/no]: no

Press RETURN to get started!

Router>config t
^
% Invalid input detected at '^' marker.

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fa 0/0
Router(config-if)#ip address 192.168.19.1 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up


%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#
```

Copy Paste

☐ Top





Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC4	Router6	ICMP		0.000	N	0	(edit)	(delete)
	Successful	PC5	Router5	ICMP		0.000	N	1	(edit)	(delete)
	Successful	PC6	Router2	ICMP		0.000	N	2	(edit)	(delete)
	Successful	Server0	Router2	ICMP		0.000	N	3	(edit)	(delete)





Router Principal

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.0.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#
Router(config-if)#exit
Router(config)#interface s 0/0/1
Router(config-if)#ip address 192.168.1.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
Router(config-if)#exit
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.2.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Router(config-if)#
```

Copy

Paste

☐ Top





Router1

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.0.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Router(config-if)#exit
Router(config)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Router(config)#interface s 0/0/1
Router(config-if)#ip address 192.168.3.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
Router(config-if)#exit
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.4.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Router(config-if)#
```

Copy

Paste

☐ Top





Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.3.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/0/1
Router(config-if)#ip address 192.168.5.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/1, changed state to down
Router(config-if)#exit
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.6.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Router(config-if)#
```

Copy Paste

☐ Top





Router3

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.1.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/0/1
Router(config-if)#ip address 192.168.5.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/0/1
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, chano shutdown
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.7.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/0, changed state to down
Router(config-if)#
```

Copy

Paste

☐ Top







Router4

Physical Config CLI Attributes

IOS Command Line Interface

```
Compiled Wed 18-Jul-07 04:52 by pt_team

Press RETURN to get started!

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.2.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Router(config-if)#exit
Router(config)#interfa
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up
c
% Incomplete command.
Router(config)#interface s 0/1/1
Router(config-if)#ip address 192.168.8.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/1/1, changed state to down
Router(config-if)#exit
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#
```

Copy Paste

☐ Top





Router5

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface s 0/1/1
      ^
% Invalid input detected at '^' marker.

Router(config)#interface s 0/1/1
Router(config-if)#ip address 192.168.8.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to up

Router(config-if)#interface s 0/1/0
Router(config-if)#ip address 192.168.4.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Router(config-if)#no shutdown
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up
Router(config-if)#exit
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.9.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#
Router(config-if)#
```

Copy Paste

☐ Top





Router6

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface s 0/1/1
Router(config-if)#ip address 192.168.9.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up

Router(config-if)#exit
Router(config)#exit
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/1, changed state to shutdown
^
% Invalid input detected at '^' marker.

Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.6.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Router(config-if)#
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up
exit
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.11.1 255.255.255.0
Router(config-if)#no shutdown

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to down
Router(config-if)#
Router(config-if)#
```

Copy

Paste

☐ Top





Router7

PhysicalConfigCLIAttributes

IOS Command Line Interface

```
Router>enable
Router#config t
Enter configuration commands, one per line.  End with CNTL/Z.
Router(config)#interface s 0/0/0
Router(config-if)#ip address 192.168.11.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/0/0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/1/0
Router(config-if)#ip address 192.168.7.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up

Router(config-if)#exit
Router(config)#interface s 0/1/1
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Router(config-if)#ip address 192.168.10.2 255.255.255.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/1/1, changed state to up


Router(config-if)#
```

Copy

Paste

☐ Top







Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

Press RETURN to get started!

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 192.168.12.0 255.255.255.0 192.168.0.1
Router(config)#ip route 192.168.17.0 255.255.255.0 192.168.4.2
Router(config)#ip route 192.168.14.0 255.255.255.0 192.168.3.2
Router(config)#
```

Copy Paste

☐ Top







Router2

Physical Config CLI Attributes

IOS Command Line Interface

```
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

Press RETURN to get started!

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up

Router>
Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 192.168.13.0 255.255.255.0 192.168.3.1
Router(config)#ip route 192.168.15.0 255.255.255.0 192.168.5.2
Router(config)#ip route 192.168.18.0 255.255.255.0 192.168.6.2
Router(config)#
```

Copy Paste

☐ Top







Router3

Physical

Config

CLI

Attributes

IOS Command Line Interface

```
2 FastEthernet/IEEE 802.3 interface(s)
4 Low-speed serial(sync/async) network interface(s)
191K bytes of NVRAM.
63488K bytes of ATA CompactFlash (Read/Write)
Cisco IOS Software, 1841 Software (C1841-ADVIPSERVICESK9-M), Version 12.4(15)T1, RELEASE
SOFTWARE (fc2)
Technical Support: http://www.cisco.com/techsupport
Copyright (c) 1986-2007 by Cisco Systems, Inc.
Compiled Wed 18-Jul-07 04:52 by pt_team

Press RETURN to get started!

%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up
%LINK-5-CHANGED: Interface Serial0/0/1, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/1, changed state to up
%LINK-5-CHANGED: Interface Serial0/1/0, changed state to up
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/1/0, changed state to up


Router>enable
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#ip route 192.168.14.0 255.255.255.0 192.168.5.1
Router(config)#ip route 192.168.12.0 255.255.255.0 192.168.1.1
Router(config)#ip route 192.168.19.0 255.255.255.0 192.168.7.2
Router(config)#
```


Copy


Paste

☐ Top











Router7

PhysicalConfigCLIAttributes

IOS Command Line Interface

Press RETURN to get started.

Router>enabel  
Translating "enabel"...domain server (255.255.255.255)  
% Unknown command or computer name, or unable to find computer address  
  
Router>enable  
Router#config t  
Enter configuration commands, one per line. End with CNTL/Z.  
Router(config)#ip route 192.168.15.0 255.255.255.0 192.168.7.1  
Router(config)#ip route 192.168.18.0 255.255.255.0 192.168.11.1  
Router(config)#ip route 192.168.16.0 255.255.255.0 192.168.10.1  
Router(config)#exit  
Router#  
%SYS-5-CONFIG\_I: Configured from console by console  
  
Router#copy run start  
Destination filename [startup-config]?  
Building configuration...  
[OK]  
Router#

Copy

Paste

☐ Top





