

```

1  /*****
2  MPLAB Harmony Application Header File
3
4  Company:
5  Microchip Technology Inc.
6
7  File Name:
8  app.h
9
10 *****/
11
12 //DOM-IGNORE-BEGIN
13 /*****
14 Copyright (c) 2013-2014 released Microchip Technology Inc. All rights reserved.
15
16 Microchip licenses to you the right to use, modify, copy and distribute
17 Software only when embedded on a Microchip microcontroller or digital signal
18 controller that is integrated into your product or third party product
19 (pursuant to the sublicense terms in the accompanying license agreement).
20
21 You should refer to the license agreement accompanying this Software for
22 additional information regarding your rights and obligations.
23
24 SOFTWARE AND DOCUMENTATION ARE PROVIDED "AS IS" WITHOUT WARRANTY OF ANY KIND,
25 EITHER EXPRESS OR IMPLIED, INCLUDING WITHOUT LIMITATION, ANY WARRANTY OF
26 MERCHANTABILITY, TITLE, NON-INFRINGEMENT AND FITNESS FOR A PARTICULAR PURPOSE.
27 IN NO EVENT SHALL MICROCHIP OR ITS LICENSORS BE LIABLE OR OBLIGATED UNDER
28 CONTRACT, NEGLIGENCE, STRICT LIABILITY, CONTRIBUTION, BREACH OF WARRANTY, OR
29 OTHER LEGAL EQUITABLE THEORY ANY DIRECT OR INDIRECT DAMAGES OR EXPENSES
30 INCLUDING BUT NOT LIMITED TO ANY INCIDENTAL, SPECIAL, INDIRECT, PUNITIVE OR
31 CONSEQUENTIAL DAMAGES, LOST PROFITS OR LOST DATA, COST OF PROCUREMENT OF
32 SUBSTITUTE GOODS, TECHNOLOGY, SERVICES, OR ANY CLAIMS BY THIRD PARTIES
33 (INCLUDING BUT NOT LIMITED TO ANY DEFENSE THEREOF), OR OTHER SIMILAR COSTS.
34 *****/
35 //DOM-IGNORE-END
36
37 #ifndef _APP_H
38 #define _APP_H
39
40 // ****
41 // ****
42 // Section: Included Files
43 // ****
44 // ****
45
46 #include <stdint.h>
47 #include <stdbool.h>
48 #include <stddef.h>
49 #include <stdlib.h>
50 #include "system_config.h"
51 #include "system_definitions.h"
52 #include "bno055.h"
53
54 // DOM-IGNORE-BEGIN
55 #ifdef __cplusplus // Provide C++ Compatibility
56
57 extern "C" {
58
59 #endif
60 // DOM-IGNORE-END
61
62
63 #define TIME_OUT 80000000U
64 #define BTN_HOLD_SHUTDOWN_x10ms 200
65 #define NB_MEASURES 2
66
67 #define ACCEL_ACTIV_DETECT_msq 0.3
68 #define T_CONFIG_TIMEOUT 20
69 #define T_INACTIVE_PERIOD_DEFAULT 20UL
70 #define T_INTERVAL_GNSS_DEFAULT 5000UL
71 #define T_INTERVAL_IMU_DEFAULT 500UL
72 #define LED_STATE_DEFAULT (uint8_t)1
73

```

```

74 #define LED_PERIOD 5
75
76 #define CHAR_READ_BUFFER_SIZE 30
77
78 #define G 9.81
79
80
81 // *****
82 // *****
83 // Section: Type Definitions
84 // *****
85 // *****
86 typedef struct {
87     s32 comres;
88     bool flagMeasReady;
89     uint8_t flagImportantMeas;
90     struct bno055_gravity_double_t gravity;
91     struct bno055_linear_accel_double_t linear_accel;
92     struct bno055_euler_double_t euler;
93     struct bno055_gyro_double_t gyro;
94     struct bno055_mag_double_t mag;
95     struct bno055_quaternion_t quaternion;
96     unsigned long time;
97     unsigned long l_time;
98     uint16_t d_time;
99 } s_bno055_data;
100 // *****
101 /* Application states
102
103     Summary:
104         Application states enumeration
105
106     Description:
107         This enumeration defines the valid application states. These states
108         determine the behavior of the application at various times.
109 */
110
111 typedef enum
112 {
113     /* Application's state machine's initial state. */
114     APP_STATE_INIT=0,
115     APP_STATE_CONFIG,
116     APP_STATE_LOGGING,
117     APP_STATE_FLAG_MEAS,
118     APP_STATE_COMM_LIVE_GNSS,
119     APP_STATE_COMM_LIVE_IMU,
120     APP_STATE_CONFIGURATE_BBX,
121     APP_STATE_SHUTDOWN
122     /* TODO: Define states used by the application state machine. */
123
124 } APP_STATES;
125
126
127 // *****
128 /* Application Data
129
130     Summary:
131         Holds application data
132
133     Description:
134         This structure holds the application's data.
135
136     Remarks:
137         Application strings and buffers are be defined outside this structure.
138 */
139
140 typedef struct
141 {
142     /* The application's current state */
143     APP_STATES state;
144
145     bool ledState;
146

```

```

147     /* TODO: Define any additional data used by the application. */
148
149 } APP_DATA;
150
151 typedef struct
152 {
153     /* DELAY DATA */
154     bool tmrTickFlag;
155     unsigned long delayCnt;
156
157     /* MEASURES DATA */
158     unsigned long measCnt[NB_MEASURES];
159     unsigned long ltime[NB_MEASURES];
160     bool measTodo[NB_MEASURES];
161     unsigned long measPeriod[NB_MEASURES];
162
163     unsigned long inactiveCnt;
164     uint32_t inactivePeriod;
165
166     /* DISPLAY DATA */
167     uint32_t ledCnt;
168
169     /* BUTTON DATA */
170     bool flagCntBtnPressed;
171     uint32_t cntBtnPressed;
172 }TIMER_DATA;
173
174 /* Measures index */
175 enum measure{BNO055_idx, GNSS_idx};
176
177 // *****
178 // *****
179 // Section: Application Callback Routines
180 // *****
181 // *****
182 /* These routines are called by drivers when certain events occur.
183 */
184
185 // *****
186 // *****
187 // Section: Application Initialization and State Machine Functions
188 // *****
189 // *****
190
191 /*****
192  Function:
193      void APP_Initialize ( void )
194
195  Summary:
196      MPLAB Harmony application initialization routine.
197
198  Description:
199      This function initializes the Harmony application. It places the
200      application in its initial state and prepares it to run so that its
201      APP_Tasks function can be called.
202
203  Precondition:
204      All other system initialization routines should be called before calling
205      this routine (in "SYS_Initialize").
206
207  Parameters:
208      None.
209
210  Returns:
211      None.
212
213  Example:
214      <code>
215      APP_Initialize();
216      </code>
217
218  Remarks:
219      This routine must be called from the SYS_Initialize function.

```

```

220 */
221
222 void APP_Initialize ( void );
223
224
225 /*****
226  Function:
227      void APP_Tasks ( void )
228
229  Summary:
230      MPLAB Harmony Demo application tasks function
231
232  Description:
233      This routine is the Harmony Demo application's tasks function.  It
234      defines the application's state machine and core logic.
235
236  Precondition:
237      The system and application initialization ("SYS_Initialize") should be
238      called before calling this.
239
240  Parameters:
241      None.
242
243  Returns:
244      None.
245
246  Example:
247      <code>
248      APP_Tasks();
249      </code>
250
251  Remarks:
252      This routine must be called from SYS_Tasks() routine.
253  */
254
255 void APP_Tasks( void );
256
257 // CALLBACKS
258 void delayTimer_callback( void );
259 void stateTimer_callback( void );
260
261 void appStateSet( APP_STATES newState );
262
263 #endif /* _APP_H */
264
265 //DOM-IGNORE-BEGIN
266 #ifdef __cplusplus
267 }
268 #endif
269 //DOM-IGNORE-END
270
271 /*****
272  End of File
273  */
274
275

```