

## MySQL Commands Cheat Sheet

### -- Database-Level

|   |   |
|---|---|
| DROP DATABASE <i>databaseName</i>                 | -- Delete the database (irrecoverable!) |
| DROP DATABASE IF EXISTS <i>databaseName</i>       | -- Delete if it exists                  |
| CREATE DATABASE <i>databaseName</i>               | -- Create a new database                |
| CREATE DATABASE IF NOT EXISTS <i>databaseName</i> | -- Create only if it does not exists    |
| SHOW DATABASES                                    | --Show all the databases in this server |
| USE <i>databaseName</i>                           | -- Set the default (current) database   |
| SELECT DATABASE()                                 | -- Show the default database            |
| SHOW CREATE DATABASE <i>databaseName</i>          | -- Show the CREATE DATABASE statement   |

### -- Table-Level

|  |  |
|--|--|
| DROP TABLE [IF EXISTS] <i>tableName</i> , ...  |  |
| CREATE TABLE [IF NOT EXISTS] <i>tableName</i>  |  |
| ( <i>columnName</i> <i>columnType</i> <i>columnAttribute</i> , ...   |  |
| PRIMARY KEY( <i>columnName</i> ),  |  |
| FOREIGN KEY ( <i>columnNmae</i> ) REFERENCES <i>tableName</i> ( <i>columnNmae</i> )                                  |  |
| )  |  |
| SHOW TABLES  | -- Show all the tables in the default database               |
| DESCRIBE DESC <i>tableName</i>   | -- Describe the details for a table                          |
| ALTER TABLE <i>tableName</i> ...   | -- Modify a table, e.g., ADD COLUMN and DROP COLUMN          |
| ALTER TABLE <i>tableName</i> ADD <i>columnDefinition</i>   |  |
| ALTER TABLE <i>tableName</i> DROP <i>columnName</i>  |  |
| ALTER TABLE <i>tableName</i> ADD FOREIGN KEY ( <i>columnNmae</i> ) REFERENCES <i>tableName</i> ( <i>columnNmae</i> ) |  |
| ALTER TABLE <i>tableName</i> DROP FOREIGN KEY <i>constraintName</i>  |  |
| SHOW CREATE TABLE <i>tableName</i>   | -- Show the CREATE TABLE statement for this <i>tableName</i> |

### -- Row-Level

|   |                               |
|---|-------------------------------|
| INSERT INTO <i>tableName</i> VALUES ( <i>column1Value</i> , <i>column2Value</i> ,...)   | -- Insert on all Columns      |
| INSERT INTO <i>tableName</i> VALUES ( <i>column1Value</i> , <i>column2Value</i> ,...), ...  | -- Insert multiple rows       |
| INSERT INTO <i>tableName</i> ( <i>column1Name</i> , ..., <i>columnNName</i> ) VALUES ( <i>column1Value</i> , ..., <i>columnNValue</i> )                           | -- Insert on selected Columns |
| DELETE FROM <i>tableName</i> WHERE <i>criteria</i>  |                               |
| UPDATE <i>tableName</i> SET <i>columnName</i> = <i>expr</i> , ... WHERE <i>criteria</i>   |                               |
| SELECT *   <i>column1Name</i> AS <i>alias1</i> , ..., <i>columnNName</i> AS <i>aliasN</i> FROM <i>tableName</i>   |                               |
| WHERE <i>criteria</i> GROUP BY <i>columnName</i> ORDER BY <i>columnName</i> ASC DESC, ... HAVING <i>groupConstraints</i> LIMIT <i>count</i>   <i>offset count</i> |                               |

### -- Others

|                |  |
|----------------|--|
| SHOW WARNINGS; | -- Show the warnings of the previous statement |
|----------------|--|

## Alter Commands:

The basic syntax of **ALTER TABLE** to add a new column in an existing table is as follows:

```
ALTER TABLE table_name ADD column_name datatype;
```

The basic syntax of **ALTER TABLE** to **DROP COLUMN** in an existing table is as follows:

```
ALTER TABLE table_name DROP COLUMN column_name;
```

The basic syntax of **ALTER TABLE** to change the **DATA TYPE** of a column in a table is as follows:

```
ALTER TABLE table_name MODIFY COLUMN column_name datatype;
```

The basic syntax of **ALTER TABLE** to add a **NOT NULL** constraint to a column in a table is as follows:

```
ALTER TABLE table_name MODIFY column_name datatype NOT NULL;
```

The basic syntax of **ALTER TABLE** to **ADD UNIQUE CONSTRAINT** to a table is as follows:

```
ALTER TABLE table_name ADD CONSTRAINT MyUniqueConstraint UNIQUE(column1, column2...);
```

The basic syntax of **ALTER TABLE** to **ADD CHECK CONSTRAINT** to a table is as follows:

```
ALTER TABLE table_name ADD CONSTRAINT MyUniqueConstraint CHECK (CONDITION);
```

The basic syntax of **ALTER TABLE** to **ADD PRIMARY KEY** constraint to a table is as follows:

```
ALTER TABLE table_name ADD CONSTRAINT MyPrimaryKey PRIMARY KEY (column1, column2...);
```

The basic syntax of **ALTER TABLE** to **DROP CONSTRAINT** from a table is as follows:

```
ALTER TABLE table_name DROP CONSTRAINT MyUniqueConstraint;
```

The basic syntax of **ALTER TABLE** to **DROP PRIMARY KEY** constraint from a table is as follows:

```
ALTER TABLE table_name DROP PRIMARY KEY;
```

Another useful link is:

[http://www.techonthenet.com/mysql/tables/alter\\_table.php](http://www.techonthenet.com/mysql/tables/alter_table.php)

More commands can be found on GOOGLE ☺ ... Keep exploring...!!