

Conexion:



Query:

The screenshot shows the 'OLE DB Source Editor' dialog box. The title bar reads 'OLE DB Source Editor'. The main text says: 'Configure the properties used by a data flow to obtain data from any OLE DB provider.'


On the left, there is a tree view with the following items: 'Administrador de conexiones OLE DB', 'Columnas', and 'Salida de error'.

The main area contains the following fields and buttons:


- 'Administrador de conexiones OLE DB:' with a dropdown menu showing 'localhost.AdventureWorksOLTP22.sa' and a 'Nueva...' button.
- 'Modo de acceso a datos:' with a dropdown menu showing 'Comando SQL'.
- 'Texto de comando SQL:' with a text area containing the following SQL query:

```
SELECT
c.CustomerID,
p.FirstName + ' ' + p.LastName AS FullName,
p.EmailPromotion,
a.City,
a.PostalCode
FROM Sales.Customer c
JOIN Person.Person p ON c.PersonID = p.BusinessEntityID
JOIN Person.BusinessEntityAddress bea ON p.BusinessEntityID =
bea.BusinessEntityID
JOIN Person.Address a ON bea.AddressID = a.AddressID;
```
- Buttons on the right: 'Parámetros...', 'Generar consulta...', 'Examinar...', and 'Analizar consulta'.
- A 'Vista previa...' button at the bottom left.
- Buttons at the bottom: 'Aceptar', 'Cancelar', and 'Ayuda'.

Vista previa:



DESTINATION:
Creacion de tabla:



OLE DB Destination Editor

— □ ×

Configure the properties used to insert data into a relational database using an OLE DB provider.

Administrador de cone

Asignaciones

Salida de error

Specify an OLE DB connection manager, a data source, or a data source view, and select the data access mode. If using the SQL command access mode, specify the SQL command either by typing the query or by using Query Builder. For fast-load data access, set the table update options.

Administrador de conexiones OLE DB:

localhost.AdventureWorks.sa

Nueva...

Modo de acceso a datos:

Carga rápida de tabla o vista

Nombre de la tabla o la vista:

[dbo].[DIMCOSTUME_2]

Nueva...

☐ Mantener valores de identidad

☒ Bloqueo de tabla

☐ Mantener valores NULL

☒ Comprobar restricciones

Filas por lote:

Tamaño máximo de confirmación de inserción:

2147483647

View Existing

⚠ Asigne las columnas en la página Asignaciones.

Aceptar

Cancelar

Ayuda

Asignaciones:

OLE DB Destination Editor

Configure the properties used to insert data into a relational database using an OLE DB provider.

Administrador de conexiones
Asignaciones
Salida de error

Columnas de entrada

Nombre
CustomerID
FullName
EmailPromotion
City

Columnas de destino

Nombre
CustomerID
FullName
EmailPromotion
City

Columna de entrada	Columna de destino
CustomerID	CustomerID
FullName	FullName
EmailPromotion	EmailPromotion
City	City
PostalCode	PostalCode

Aceptar Cancelar Ayuda