

05/10/2020


CN Lab 3

Learnings:

1. Creating a multiple router topology by connecting routers through *serial ports* and PC-router through *fast ethernet*.
2. Assigning ip addresses(gateway) to routers using the same method as in lab 2 and PCs
3. Pinging PC1 from PC0 at this state gives *destination host unreachable* in the first try
4. Viewing the routers ip routes using show ip route
5. Adding static routes to the routers using *ip route <dest. network> <subnet mask> <next hop>* in privileged (enable) configure (configure terminal) mode.
6. Pinging PC1 from PC0 and PC0 from PC1 now works as expected.

Screenshots:

Connection/topology



Router0

Physical Config CLI Attributes

IOS Command Line Interface

```
% Invalid input detected at '^' marker.

Router>enable
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, Serial2/0
S    30.0.0.0/8 [1/0] via 20.0.0.2
S    40.0.0.0/8 [1/0] via 20.0.0.2

Router#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top

Router1

Physical Config CLI Attributes

IOS Command Line Interface

```
Router>enable
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set


S    10.0.0.0/8 [1/0] via 20.0.0.1
C    20.0.0.0/8 is directly connected, Serial2/0
C    30.0.0.0/8 is directly connected, Serial3/0
S    40.0.0.0/8 [1/0] via 30.0.0.2

Router#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



Terminal

