


ARYAMAN MISHRA


19BCE1027

LAB 1

1. Create topology with 2 switches, 2 routers and 6 PC Devices.



2. Insert IPv4 Address in the config menu of the routers and turn them on.



Router1

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

Serial0/0/0

FastEthernet0/0

Port Status ☒ On

Bandwidth ☐ 100 Mbps ☐ 10 Mbps ☒ Auto

Duplex ☐ Half Duplex ☒ Full Duplex ☒ Auto

MAC Address 0090.0C45.3B01

IP Configuration

IPv4 Address 192.168.20.1

Subnet Mask 255.255.255.0

Tx Ring Limit 10

Equivalent IOS Commands

```
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to up

Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
```

☐ Top

Router1

Physical **Config** CLI Attributes

GLOBAL

Settings

Algorithm Settings

ROUTING

Static

RIP

SWITCHING

VLAN Database

INTERFACE

FastEthernet0/0

FastEthernet0/1

Serial0/0/0

Serial0/0/0

Port Status ☒ On

Duplex ☒ Full Duplex

Clock Rate 2000000

IP Configuration

IPv4 Address 192.168.30.3

Subnet Mask 255.255.255.0

Tx Ring Limit 10

Equivalent IOS Commands

```
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface Serial0/0/0
Router(config-if)#clock rate 128000
This command applies only to DCE interfaces
Router(config-if)#clock rate 2000000
This command applies only to DCE interfaces
Router(config-if)#
```

☐ Top

3. Enter IPv4 Address and Default gateway in the config menus of the PCs and set their interfaces to static.

The screenshot shows the configuration window for PC0. The 'Desktop' tab is selected. Under 'IP Configuration', the 'Static' radio button is chosen. The IPv4 Address is set to 192.168.10.2, Subnet Mask to 255.255.255.0, Default Gateway to 192.168.10.1, and DNS Server to 0.0.0.0. The IPv6 Configuration section shows 'Static' selected, with empty fields for IPv6 Address, Link Local Address, Default Gateway, and DNS Server. The 802.1X section has 'Use 802.1X Security' unchecked, Authentication set to MD5, and empty fields for Username and Password. A 'Top' button is at the bottom left.

Interface	FastEthernet0
IP Configuration	
<input type="radio"/> DHCP <input checked="" type="radio"/> Static	
IPv4 Address	192.168.10.2
Subnet Mask	255.255.255.0
Default Gateway	192.168.10.1
DNS Server	0.0.0.0
IPv6 Configuration	
<input type="radio"/> Automatic <input checked="" type="radio"/> Static	
IPv6 Address	
Link Local Address	FE80::201:97FF:FEC1:B6E6
Default Gateway	
DNS Server	
802.1X	
<input type="checkbox"/> Use 802.1X Security	
Authentication	MD5
Username	
Password	

☐ Top

The screenshot shows the configuration window for PC1. The 'Desktop' tab is selected. Under 'IP Configuration', the 'Static' radio button is chosen. The IPv4 Address is set to 192.168.10.3, Subnet Mask to 255.255.255.0, Default Gateway to 192.168.10.1, and DNS Server to 0.0.0.0. The IPv6 Configuration section shows 'Static' selected, with empty fields for IPv6 Address, Link Local Address, Default Gateway, and DNS Server. The 802.1X section has 'Use 802.1X Security' unchecked, Authentication set to MD5, and empty fields for Username and Password. A 'Top' button is at the bottom left.

Interface	FastEthernet0
IP Configuration	
<input type="radio"/> DHCP <input checked="" type="radio"/> Static	
IPv4 Address	192.168.10.3
Subnet Mask	255.255.255.0
Default Gateway	192.168.10.1
DNS Server	0.0.0.0
IPv6 Configuration	
<input type="radio"/> Automatic <input checked="" type="radio"/> Static	
IPv6 Address	
Link Local Address	FE80::2D0:58FF:FEE7:AE4C
Default Gateway	
DNS Server	
802.1X	
<input type="checkbox"/> Use 802.1X Security	
Authentication	MD5
Username	
Password	

☐ Top

PC3

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.20.2

Subnet Mask 255.255.255.0

Default Gateway 192.168.20.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::202:16FF:FE67:1754

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

PC2

Physical Config **Desktop** Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.10.4

Subnet Mask 255.255.255.0

Default Gateway 192.168.10.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::2E0:F9FF:FE33:5040

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

PC4

Physical Config Desktop Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.20.3

Subnet Mask 255.255.255.0

Default Gateway 192.168.20.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::201:96FF:FEBD:1C36

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security

Authentication MD5

Username

Password

Top

PC5

Physical Config Desktop Programming Attributes

IP Configuration X

Interface FastEthernet0

IP Configuration

☐ DHCP ☒ Static

IPv4 Address 192.168.20.4

Subnet Mask 255.255.255.0

Default Gateway 192.168.20.1

DNS Server 0.0.0.0

IPv6 Configuration

☐ Automatic ☒ Static

IPv6 Address /

Link Local Address FE80::260:5CFF:FE92:8A15

Default Gateway

DNS Server

802.1X

☐ Use 802.1X Security



Authentication MD5

Username


Password

Top

4.Add WIC-IT Port to connect the routers,and turn them on.



5. Define IP Route and Serial Port in the CLI menu of the routers.



Router0

Physical Config **CLI** Attributes

IOS Command Line Interface

```
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up

%LINK-5-CHANGED: Interface Serial0/2/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/2/0, changed state to
up


Router(config-if)#exit
Router(config)#interface Serial0/0/0
%Invalid interface type and number
Router(config)#interface Serial 0/0/0
%Invalid interface type and number
Router(config)#interface Serial 0/2/0
Router(config-if)#exit
Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.30.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top



Router1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
This command applies only to DCE interfaces
Router(config-if)#ip address 192.168.30.3 255.255.255.0
Router(config-if)#ip address 192.168.30.3 255.255.255.0
Router(config-if)#
Router(config-if)#exit
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 192.168.20.1 255.255.255.0
Router(config-if)#ip address 192.168.20.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up

Router(config-if)#exit
Router(config)#interface Serial0/0/0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface Serial0/0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial0/0/0, changed state to
up

Router(config-if)#exit
Router(config)#ip route 0.0.0.0 0.0.0.0 192.168.30.1
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console







Router#
```







Ctrl+F6 to exit CLI focus





Copy Paste

☐ Top

6. Test proper connection of the PC devices using the simulation menu.

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC0	PC4	ICMP		0.000	N	7	(edit)	(delete)
	Successful	PC0	Router0	ICMP		0.000	N	8	(edit)	(delete)
	Successful	PC0	PC3	ICMP		0.000	N	9	(edit)	(delete)

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC1	PC5	ICMP		0.000	N	10	(edit)	(delete)
	Successful	PC1	PC2	ICMP		0.000	N	11	(edit)	(delete)
	Successful	PC2	PC3	ICMP		0.000	N	12	(edit)	(delete)

Fire	Last Status	Source	Destination	Type	Color	Time(sec)	Periodic	Num	Edit	Delete
	Successful	PC1	PC2	ICMP		0.000	N	11	(edit)	(delete)
	Successful	PC2	PC3	ICMP		0.000	N	12	(edit)	(delete)

CONCLUSION:

DESIGNED TOPOLOGY HAS BEEN EXECUTED SUCCESSFULLY.