



Nama : Aulia Rachmawati

Nim : L200160015


Kelas : A

Modul 4


1. Konfigurasi TP-link menjadi access point (192.168.1.254).



2. Mengubah IP address pada PC untuk Access Point (192.168.1.12).



3. Menghubungkan Acces point kita dengan access point milik teman, kemudian melakukan ping ke PC target(teman).



4. Mengkonfigurasi Engenius menjadi Client-Bridge.

The following screenshots illustrate the configuration process for setting an Engenius device as a Client Bridge.

Screenshot 1: System Properties

The **System Properties** page shows the initial configuration options:

- Device Name:** EOC2611P (1 to 32 characters)
- Country/Region:** Please Select a Country Code
- Operation Mode:** Access Point, Client Bridge (selected), WDS Bridge, Client Router

Buttons: Apply, Cancel

Screenshot 2: Wireless Network

The **Wireless Network** page shows the wireless configuration options:

- Wireless Mode:** 802.11b/g Mixed (2GHz/54Mbps)
- SSID:** Specify the static SSID : ROZAQUE TEAM (1 to 32 characters). Or press the button to search for any available WLAN Service. (Site Survey button)
- Prefer BSSID:** E8 : DE : 27 : B7 : F6 : 78
- WDS Client:** Enable (selected), Disable

Buttons: Apply, Cancel

Screenshot 3: Main

The **Main** page displays the system information and settings:

System Information

Device Name	EOC2611P
Ethernet MAC Address	00:02:6f:94:4d:a6
Wireless MAC Address	00:02:6f:94:4d:a7
Country	N/A
Current Time	Sat Jan 1 07:43:06 UTC 2000
Device Uptime	0 Days 0 Hours 43 Mins
Firmware Version	1.3.1
Auto Reboot Settings	Disabled

LAN Settings


IP Address	192.168.1.1
Subnet Mask	255.255.255.0
Default Gateway	0.0.0.0
DHCP Client	Disabled

Current Wireless Settings

Operation Mode	Client Bridge
Wireless Mode	IEEE 802.11b/g Mixed
Frequency/Channel	2.412GHz (Channel 01)
Wireless Network Name (SSID)	ROZAQUE TEAM
Security	Disabled
Spanning Tree Protocol	Disabled
Distance	1 Km

Buttons: Refresh

5. Mengubah IP address pada PC untuk Client Bridge(192.168.1.150).



6. Menghubungkan Client-Bridge kita dengan Client-Bridge milik teman, kemudian melakukan ping ke PC target(teman).

