

Existing UI

Home

Business Process >

Masters >

Company Settings >

View / Edit Item Master

Manufactured Part

Assembly

BOF

Raw Material

Status

Company

enter here

Part Number

enter here

Part Description

enter here

Keyword / Description

Remove Keyword / Description

Left Justify Column Headings

Company	Part No	Description	Notes	
TISS Ltd	T-1046	06 Head	06 Head	...
TISS Ltd	T-1069	Ring	Ring	...
TISS Ltd	T-1053	Dome Base	Dome Base	...
TISS Ltd	T-1056	Tube	Tube	...
TISS Ltd	T-1011A	Top Tube	Top Tube	...

Use 3 Columns of equal width

Replace Notes with Part Type

View / Edit Item Master

Part Type

Choose from Drop down

Customer

Choose from Drop down

Status

Choose from Drop down

Part Number

Enter Part Number

Part Desc

Enter Part Description

Manufactured Part without RM

Assembly Part No without BOM

RM without Supplier

Retain Grid with changes shown above
Reduce the spacing between Grid & Filter Section

Manufactured Parts / Assemblies Overview



Company	# Manf Parts (Active)	# Assemblies (Active)	# Manf Parts (Inactive)	# Assemblies (Inactive)	# Active Manf Part w/o RM	# Active Assemblies w/o BOM	View List
Total	xxx	xxx	xxx	xxx	xxx	xxx	

#Manf Parts (Active) =
Count of Manf Parts
in Item Master
(for Company)

Active Manf Part
w/o RM = count of Manf
Part without Linked RM
(for Company)

Total for each column will
be outside the grid

When View Icon
clicked it will call
popup below

Manufactured Part / Assembly List for Company xxxx



Part Type

Status

Manufactured Part
without RM ☐

Assembly Part No
without BOM ☐

Part No / Description / Rev No / Date	Part Type	Status	Status Change Date	RM Linked	BOM Avl	View Doc
xxxx	Manf Part	Active		Yes	-	
xxxx	Assy	Inactive		-	No	

When View List is selected
this Popup will be called
Part Type = Manf Part or
Assy
Status = Active / Inactive
If Manufactured Part does
not have a raw material
linked then RM Linked = No
If Assembly does not have
a BOM then BOM Avl = No

When View Icon is
clicked it will call
the Document
Viewer

Raw Material Overview



Supplier / Customer	Source	# Made to Print	# Standard RM	#Catalog	# Preferred	# Inactive	View List



When View Icon clicked it will call popup below

Raw Material / Input Matl List for Company xxxx

Customer Supplied



RM Type

Status

Base RM

Part No / Description / Rev No / Date	RM Type	Status	Status Change Date	Base RM	Matl Spec	View Doc
xxxx	Forging	Active			-	
xxxx	Casting	Inactive		-		




Customer Supplied Text Box is shown when Source = Customer Supplied RM

Source = Own Purchased RM this text box is not shown

When View Icon is clicked it will call the Document Viewer

BOF Overview

X

Supplier / Customer	Source	# Made to Print	# Standard	#Catalog	# Preferred	# Inactive	View List
							


When View Icon clicked it will call popup below

BOF Type = Made to Print, Standard & Catalog

Source = Customer Supplied BOF, Own Purchased

BOM List for Company xxxx


X

BOF Type 

Status 

Base RM 

Customer Supplied

Part No / Description / Rev No / Date	BOF Type	Status	Status Change Date	Base RM	Matl Spec	View Doc
xxxx	Forging	Active			-	
xxxx	Casting	Inactive		-		

Customer Supplied Text Box is shown when Source = Customer Supplied RM

Source = Own Purchased RM this text box is not shown

When View Icon clicked it will the document viewer

Document Viewer Popup

View Documents

X

Document Type : xxxx Uploaded by xxxx on xxxxx
Retention Date : xx-xx-xxxx

Part No / Desc : xxxx / xxxx Customer : xxxx

Popup to view document

Provide Document View controls - Zoom in / zoom out, ... typically available with pdf viewer

The Calling program for the viewer to provide the content for the Header