

Valentine:

enable

config terminal

On fastethernet 5/0 interface:

interface fastethernet 5/0

ip address 192.0.8.1 255.255.255.0

no shutdown

exit

On serial 9/0 interface:

interface serial 9/0

ip address 192.0.9.41 255.255.255.252

clock rate 64000

no shutdown

Exit

Strawberry:

enable

config terminal

On interface fastethernet 6/0:

interface fastethernet 6/0

ip address 192.0.7.1 255.255.255.0

no shutdown

exit

1

On interface serial 8/0:

interface serial 2/0

ip address 192.0.9.42 255.255.255.252

no shutdown

exit

On interface serial 9/0:

interface serial 3/0

ip address 192.0.9.33 255.255.255.252

clock rate 64000

no shutdown

exit

Annesburg:

enable

config terminal

On interface fastethernet 2/0:

interface fastethernet 2/0

ip address 192.0.9.1 255.255.255.224

no shutdown

```
exit
On interface serial 4/0:
interface serial 4/0
ip address 192.0.9.53 255.255.255.252
no shutdown
exit
On interface serial 5/0:
interface serial 5/0
ip address 192.0.9.45 255.255.255.252
clock rate 2000000
no shutdown
exit
On interface serial 6/0:
interface serial 6/0
ip address 192.0.9.34 255.255.255.252
clock rate 2000000
no shutdown
Exit
```

```
Rhodes:
enable
config t
On interface fastethernet 5/0:
interface fastethernet 5/0
ip address 192.0.4.1 255.255.254.0
no shutdown
exit
On interface serial 6/0:
interface serial 6/0
ip address 192.0.9.54 255.255.255.252
clock rate 2000000
no shutdown
exit
On interface serial 9/0:
interface serial 9/0
ip address 192.0.9.38 255.255.255.252
3
no shutdown
Exit
```

Saint Denis

```
enable
config t
On interface fastethernet 5/0:
interface fastethernet 5/0
ip address 192.0.0.1 255.255.252.0
no shutdown
exit
On interface serial 7/0:
interface serial 7/0
4
ip address 192.0.9.50 255.255.255.252
no shutdown
exit
On interface serial 8/0:
interface serial 8/0
ip address 192.0.9.37 255.255.255.252
clock rate 64000
no shutdown
exit
On interface serial 9/0:
interface serial 9/0
ip address 192.0.9.46 255.255.255.252
no shutdown
Exit
```

Lympny:

```
enable
config t
On interface fastethernet 5/0:
interface fastethernet 5/0
ip address 192.0.6.1 255.255.255.0
no shutdown
exit
On interface serial 9/0:
interface serial 9/0
ip address 192.0.9.49 255.255.255.252
no shutdown
Exit
```

