

Untitled Model 2

K2 STORAGE 2;  
K4 STORAGE 3;  
K5 STORAGE 4;  
  
GENERATE 6,3;  
TRANSFER BOTH,METK1,METK2;  
  
METK1 SEIZE PRU1;  
ADVANCE 25,4;  
RELEASE PRU1;  
  
TRANSFER, STK;  
  
METK2 ENTER K2;  
ADVANCE 25,6;  
LEAVE K2;  
  
STK TRANSFER BOTH,METK3,METK4;  
METK3 SEIZE PRU2;  
ADVANCE 25,6;  
RELEASE PRU2;  
  
TRANSFER, STK2;  
  
METK4 ENTER K4;  
ADVANCE 25,4;  
LEAVE K4;  
  
STK2 GATE SNF K5,OUT;  
ENTER K5;  
ADVANCE 20,5;  
LEAVE K5;  
  
OUT TERMINATE 1;  
START 100;

Untitled Model 2.5.sim - JOURNAL

03/06/23 21:03:06 Model Translation Begun.  
03/06/23 21:03:06 Ready.  
03/06/23 21:03:06 Simulation in Progress.  
03/06/23 21:03:06 The Simulation has ended. Clo  
03/06/23 21:03:06 Reporting in Untitled Model 2.5.1 - REPORT Window.

Untitled Model 2.5.1 - REPORT

GPSS World Simulation Report - Untitled Model 2.5.1

Monday, March 06, 2023 21:03:06

START TIME      END TIME    BLOCKS    FACILITIES    STORAGES  
0.000            1313.515    22        2            3


NAME            VALUE  
K2              10000.000  
K4              10001.000  
K5              10002.000  
METK1           3.000  
METK2           7.000  
METK3           11.000  
METK4           15.000  
OUT             22.000  
PRU1            10003.000  
PRU2            10004.000  
STK             10.000  
STK2            18.000

LABEL           LOC    BLOCK TYPE    ENTRY COUNT    CURRENT COUNT    RETRY  
1    GENERATE    215           0           0  
2    TRANSFER    215           108          0  
3    SEIZE        53           0           0  
4    ADVANCE     53           1           0  
5    RELEASE     52           0           0  
6    TRANSFER    52           0           0  
7    ENTER       106           0           0  
8    ADVANCE    106           2           0  
9    LEAVE       104           0           0  
10   TRANSFER    104           0           0  
11   SEIZE       40           0           0  
12   ADVANCE    40           1           0  
13   RELEASE    39           0           0  
14   TRANSFER   39           0           0  
15   ENTER      103           0           0

Активация Windows  
Чтобы активировать Windows, зайдите в меню  
"Параметры".

For Help, press F1

Report is Complete.



Untitled Model 2

K2 STORAGE 2;  
K4 STORAGE 3;  
K5 STORAGE 4;  
  
GENERATE 6,3;  
TRANSFER BOTH,METK1,METK2;  
  
METK1 SEIZE PRU1;  
ADVANCE 25,4;  
RELEASE PRU1;  
  
TRANSFER, STK;  
  
METK2 ENTER K2;  
ADVANCE 25,6;  
LEAVE K2;  
  
STK TRANSFER BOTH,METK3,METK4;  
METK3 SEIZE PRU2;  
ADVANCE 25,6;  
RELEASE PRU2;  
  
TRANSFER, STK2;  
  
METK4 ENTER K4;  
ADVANCE 25,4;  
LEAVE K4;  
  
STK2 GATE SNF K5,OUT;  
ENTER K5;  
ADVANCE 20,5;  
LEAVE K5;  
  
OUT TERMINATE 1;  
START 100;

Untitled Model 2.5.sim - JOURNAL

03/06/23 21:03:06 Model Translation Begun.  
03/06/23 21:03:06 Ready.  
03/06/23 21:03:06 Simulation in Progress.  
03/06/23 21:03:06 The Simulation has ended. Clo  
03/06/23 21:03:06 Reporting in Untitled Model 2.5.1 - REPORT Window.

Untitled Model 2.5.1 - REPORT

4    ADVANCE    53           1           0  
5    RELEASE    52           0           0  
6    TRANSFER   52           0           0  
7    ENTER      106           0           0  
8    ADVANCE   106           2           0  
9    LEAVE      104           0           0  
10   TRANSFER   104           0           0  
11   SEIZE       40           0           0  
12   ADVANCE    40           1           0  
13   RELEASE    39           0           0  
14   TRANSFER   39           0           0  
15   ENTER      103           0           0  
16   ADVANCE   103           2           0  
17   LEAVE      101           0           0  
18   GATE       101           0           0  
19   ENTER      101           0           0  
20   ADVANCE   101           1           0  
21   LEAVE      100           0           0  
22   TERMINATE  100           0           0

FACILITY        ENTRIES    UTIL.    AVE. TIME AVAIL.    OWNER    PEND    INTER    RETRY    DELAY  
PRU1            53    0.994    24.631    1        107    0    0    108    0  
PRU2            40    0.756    24.835    1        105    0    0    0    0

STORAGE        CAP.    REM.    MIN.    MAX.    ENTRIES    AVL.    AVE.C.    UTIL.    RETRY    DELAY  
K2              2    0    0    2        106    1    1.973    0.986    108    0  
K4              3    1    0    3        103    1    1.921    0.640    0    0  
K5              4    3    0    3        101    1    1.549    0.387    0    0

FEC XN    PRI        BDT        ASSEM    CURRENT    NEXT    PARAMETER    VALUE  
216    0        1313.554    216        0        1  
101    0        1316.785    101        20        21  
106    0        1319.371    106        8        9  
103    0        1324.249    103        16        17  
102    0        1325.503    102        16        17  
104    0        1325.797    104        8        9  
105    0        1328.021    105        12        13  
107    0        1329.511    107        4        5

Активация Windows  
Чтобы активировать Windows, зайдите в меню  
"Параметры".

For Help, press F1

Report is Complete.