

Installation et configuration proxmox

Proxmox VE 8.2 (iso release 2) - <https://www.proxmox.com/>



Welcome to Proxmox Virtual Environment

[Install Proxmox VE \(Graphical\)](#)
[Install Proxmox VE \(Terminal UI\)](#)
[Advanced Options](#)



Proxmox VE Installer

Proxmox Virtual Environment (PVE)

The Proxmox Installer automatically partitions your hard disk. It installs all required packages and makes the system bootable from the hard disk. All existing partitions and data will be lost.

Press the Next button to continue the installation.

- **Please verify the installation target**
The displayed hard disk will be used for the installation.
Warning: All existing partitions and data will be lost.
- **Automatic hardware detection**
The installer automatically configures your hardware.
- **Graphical user interface**
Final configuration will be done on the graphical user interface, via a web browser.

Target Harddisk /dev/sda (119.24GiB, Hoodisk SSD) ▼

Options



Proxmox VE Installer

Location and Time Zone selection

The Proxmox Installer automatically makes location-based optimizations, like choosing the nearest mirror to download files from. Also make sure to select the correct time zone and keyboard layout.

Press the Next button to continue the installation.

- **Country:** The selected country is used to choose nearby mirror servers. This will speed up downloads and make updates more reliable.
- **Time Zone:** Automatically adjust daylight saving time.
- **Keyboard Layout:** Choose your keyboard layout.

Country

Time zone Europe/Vienna ▼

Keyboard Layout U.S. English ▼



Proxmox VE Installer

Management Network Configuration

Please verify the displayed network configuration. You will need a valid network configuration to access the management interface after installing.

After you have finished, press the Next button. You will be shown a list of the options that you chose during the previous steps.

- **IP address (CIDR):** Set the main IP address and netmask for your server in CIDR notation.
- **Gateway:** IP address of your gateway or firewall.
- **DNS Server:** IP address of your DNS server.

Management Interface: enp2s0 - 68:1d:ef:26:81:6a (igc)

Hostname (FQDN): pve.example.invalid

IP Address (CIDR): 192.168.50. / 24

Gateway: 192.168.100.1

DNS Server: 127.0.0.1



Proxmox VE Installer

Summary

Please confirm the displayed information. Once you press the **Install** button, the installer will begin to partition your drive(s) and extract the required files.

Option	Value
Filesystem:	ext4
Disk(s):	/dev/sda
Country:	France
Timezone:	Europe/Paris
Keymap:	fr
Email:	a@a.fr
Management Interface:	enp2s0
Hostname:	pve-j4125
IP CIDR:	192.168.50.17/24
Gateway:	192.168.50.254
DNS:	192.168.50.254



Proxmox VE Installer

Installation successful!

Proxmox VE is now installed and ready to use.

- **Next steps**

Reboot and point your web browser to the selected IP address on port 8006:

`https://192.168.50.17:8006`

Also visit www.proxmox.com for more information.

Automatic reboot scheduled in 4 seconds.