

Input field contains multiple lines. Each line is an individual input that is required to get to the respective test case if the user were to have just started the program. That is, the input field:

login

ATM

logout

would represent the inputs: login > (PRESS ENTER)> ATM > (PRESS ENTER) > logout > (PRESS ENTER)

It is also important to note that inputs are not case sensitive. Every input will be formatted to be lower case. The only exception would be inputs related to names, as names are case-sensitive.

### logout:

Requirement	Test No.	Test Name	Purpose	Input	Input Files	Output	Output Files
End Processing Day	R5T1	ATM session logout	Allow the user to logout if they are in an active session	login ATM logout	none	Logging out...	R5T1_transaction_summary_file.txt
	R5T2	Agent session logout	Allow the user to logout if they are in an active session	login Agent logout	none	Logging out...	R5T2_transaction_summary_file.txt
no other transactions other than login after logging out  (It is important to note that logging out as an agent or atm will bring you to the same idle state so we will only test with ATM)	R6T1	logged out logout	User cannot logout after logging out	login ATM logout logout	none	Error: You must login before you can logout. Please type login:	none
	R6T2	logged out createaccount	User cannot create account after logging out	login ATM logout createaccount	none	Error: You must login as an agent before creating an account. Please type login:	none
	R6T3	logged out deleteaccount	User cannot delete account after logging out	login ATM logout deleteaccount	none	Error: You must login as an agent before deleting an account. Please type login:	none
	R6T4	logged out deposit	User cannot deposit after logging out	login ATM logout deposit	none	Error: You must login before	none

						you can deposit. Please type login:	
	R6T5	logged out withdraw	User cannot withdraw after logging out	login ATM logout withdraw	none	Error: You must login before you can withdraw . Please type login:	none
	R6T7	logged out transfer	User cannot transfer after logging out	login ATM logout transfer	none	Error: You must login before you can transfer . Please type login:	none
	R6T8	logged out unknown	Deal with an unknown input	login ATM logout dog	none	Error: Unknown input. Please type login:	none
	R6T9	logged out login	Allow the user to login and chose login type	login ATM logout login	none	Please enter session type (ATM or Agent):	none