

# CrowdCoin Masternode Windows Hot Wallet Guide

First go to <https://github.com/crowdcoinChain/Crowdcoin/releases> and download the wallet after it Synchronizes go to Receive Tab and created an address

Overview Send Receive Transactions Masternodes

Use this form to request payments. All fields are **optional**.

Label:

Amount:  CRC

Message:

☐ Reuse an existing receiving address (not recommended)

☒ Request InstantSend

Requested payments history

Date	Label	Message	Amount (CRC)
2017-22:05	Masternode TEST	(no message)	(no amount)

Remove

no masternode payments


Synchronizing additional data: 0.00%

CRC 0.00


**Step 1:** Sent exactly 1000\* CRC to your address

- You must account Transaction Fee
- You should have more than 1000CRC in your wallet before sending

## Step 2: Wait For at least 15 Confirmations



## Step 3: Go to: Tools-> Open Wallet configuration file (It will be empty)




## Step 4: Copy the below code into the file (let it open)


masternode=1

masternodeprivkey=

externalip=




**Step 5: Go to Tools-> Debug Console -> Type masternode genkey and press enter**



**Step 6: Copy the Masternode key in to the masternodeprivkey=**

It will look like that

**masternodeprivkey= 124FqareKkDeXE5NstcVG4xpjvXAgGRA5n4SeeRjTmRn2z9BY8h**



```
crowdcoin.conf - Notepad
File Edit Format View Help
masternode=1
masternodeprivkey=124FqareKkDeXE5NstcVG4xpjvXAgGRA5n4SeeRjTmRn2z9BY8h
externalip=
```

**Step 7:** Copy your external IP (IPv4) address in to the externalip lane

It should look like this

```
externalip= 79.285.230.52
```

If you don't know your IPV4 just go to <http://whatismyip.host/>

NOTE\*: You must have Port 12865 Open

If you don't know how to do it google: How to open ports in "your router" and see the guide

If Ports are not open it will not work so be sure to open the ports

So this is how It should look like but of course remember that you should add your Masternode key and your Ip not the ones provided in the guide




```
crowdcoin.conf - Notepad
File Edit Format View Help
masternode=1
masternodeprivkey=12TrUZkRjw2X34BBBcoZXuCYvd8FdrMV8SGgg3aAf8ctoXZGh1R
externalip=79.285.230.52
```

**Step 8:** Save the crowdcoin.conf file and Close the wallet.

Wait 10 Seconds

Start The wallet

**Step 9:** Go to Tools-> Debug console and Type masternode start



OK That's IT



## FAQ

**Q: How do I add nodes?**

**A: Go to Ann thread and select the node List copy it and past it in the wallet confirmation file**

**Then Save and restart the wallet**

Your file should look like this Note\* these are not real nodes only an example

masternode=1

masternodeprivkey=12TrUZkRjw2X34BBBCoZXuCYvd8FdrMV8SGgg3aAf8ctoXZGh1R

externalip=79.204.230.52

addnode=80.209.235.89:12865

addnode=80.175.235.89:12865

addnode=22.209.235.89:12865

addnode=45.209.235.89:12865

**Q: when I enter “masternode start” is says**

“Not capable masternode: Could not connect to 79.204.230.52:12865”

**A: This problem occurs when the port is not open or you put false IPV4**

**Q: Ok port is opened IP is correct still the same message**

**A: Try the same process on another location with a different Router if you succeed then the problem lies with your router**

For some reason some Routers don't allow the Masternode to work correctly or not at all. I had this problem with a Telekom speedport 740w router Somedays it was working properly some days not at all

**Q: It says masternode not found on the list**

**A: This occurs when you have not properly send the coins at the number of 1000 exactly.**

Just be sure do it in a clean wallet and make a new address and send exactly 1000 CRC

**Q: Where do I see my Masternode**

**A: Go to Masternode Tab and then to All masternodes and search your IP or Wallet address**

If you can't see a Masternode tab go to Settings-> Option-> Wallet-? Check the Show Masternode tab