

WARRANTYASSET

Table that carries the assets of the warranty

Table

psdi.app.contract.warranty.WarrantyAssetSet

UniqueID: WARRANTYASSETID

Primary key: WARRANTYASSETID + CONTRACTNUM + REVISIONNUM + ORGID + ASSETID

LOGICAL RELATIONSHIPS

WARRANTYASSET FOREIGN KEYS

Object(Parent Keys)	Target Object(Target Keys)	Rel Number	Description
<u>CONTRACT</u> (CONTRACTNUM, REVISIONNUM, ORGID)	<u>WARRANTYASSET</u> (CONTRACTNUM, REVISIONNUM, ORGID)	1 to many	Contract
<u>LOCATIONS</u> (SITEID, LOCATION)	<u>WARRANTYASSET</u> (LOCATIONSITE, LOCATION)	1 to many	Warranty Location
<u>ORGANIZATION</u> (ORGID)	<u>WARRANTYASSET</u> (ORGID)	1 to many	Organization for the record

COLUMNS

Attribute	Modifier	Title	Remarks	SameAsAttrib	SameAsObject
WARRANTYASSETID	Required	Unique Id	Unique Id		
CONTRACTNUM	Required	Contract	Contract Number	CONTRACTNUM	<u>CONTRACT</u>
REVISIONNUM	Required	Revision	Revision Number	REVISIONNUM	<u>CONTRACT</u>
ORGID	Required	Org ID	Organization identifier	ORGID	<u>ORGANIZATION</u>
ASSETID		Asset ID	Asset identifier	ASSETID	<u>ASSET</u>
LOCATION		Location	Location to which the warranty applies.	LOCATION	<u>LOCATIONS</u>
ASSETNUM	Nonperistent	Asset	A unique identification number assigned to the asset indicated.	ASSETNUM	<u>ASSET</u>
SITEID	Nonperistent	Site	Site identifier	SITEID	<u>SITE</u>
ASSETTYPE		Asset Type	The predefined type of this asset.	ASSETTYPE	<u>ASSET</u>
LOCATIONSITE		Location site	Site identifier of the Location	SITEID	<u>SITE</u>

MAXIMO RELATIONSHIPS

MAXIMO OUTGOING RELATIONSHIPS

Name	Target	Remarks	Where Clause	Cardinality
ASSET	<u>ASSET</u>	Relationship to the Asset table, used to find all asset for a given contract asset. (warrantyasset.assetid=asset.assetid and moved=no). The resulting set will contain zero or one object.	assetid=:assetid and moved=:no	UNDEFINED
QUERYASSET	<u>ASSET</u>	Relationship to the Asset table, used to find all assets for a given contract asset. (warrantyasset.assetid=asset.assetid). The resulting set will contain zero or one object.	assetid=:assetid	UNDEFINED
LOCATION	<u>CONLINEASSET</u>	Relationship to the ContLineAsset table, used to find all lines that are related to a particular location for a given warranty contract. (warrantyasset.location = contlineasset.location and warrantyasset.revisionnum=contlineasset.revisionnum and warrantyasset.orgid=contlineasset.orgid). The resulting set will contain zero or more objects.	contractnum=:contractnum and revisionnum=:revisionnum and orgid=:orgid and location=:location	UNDEFINED
CONLINEASSET	<u>CONLINEASSET</u>	Relationship to the ContLineAsset table, used to find all lines that are related to a particular asset for a given warranty contract. (warrantyasset.contractnum = contlineasset.contractnum and warrantyasset.revisionnum=contlineasset.revisionnum and warrantyasset.orgid=contlineasset.orgid and warrantyasset.assetid=contlineasset.assetid). The resulting set will contain zero or more objects.	contractnum=:contractnum and revisionnum=:revisionnum and orgid=:orgid and assetid=:assetid	UNDEFINED

Name	Target	Remarks	Where Clause	Cardinality
CONTLINEASSETLOC	<u>CONTLINEASSET</u>	Relationship to the ContLineAsset table, used to find all lines that are related to a particular asset for a given warranty contract. (warrantyasset.contractnum = contlineasset.contractnum and warrantyasset.revisionnum=contlineasset.revisionnum and warrantyasset.orgid=contlineasset.orgid and warrantyasset.location=contlineasset.location and warrantyasset.locationsite=contlineasset.locationsite). The resulting set will contain zero or more objects.	contractnum=:contractnum and revisionnum=:revisionnum and orgid=:orgid and location=:location and locationsite=:locationsite	UNDEFINED
CONTLINEASSETTYP	<u>CONTLINEASSET</u>	Relationship to the ContLineAsset table, used to find all lines that are related to a particular assettype for a given warranty contract. (warrantyasset.contractnum = contlineasset.contractnum and warrantyasset.revisionnum=contlineasset.revisionnum and warrantyasset.orgid=contlineasset.orgid and warrantyasset.assettype=contlineasset.assettype. The resulting set will contain zero or more objects.	contractnum=:contractnum and revisionnum=:revisionnum and orgid=:orgid and assettype=:assettype	UNDEFINED
DRILLDOWN	<u>DRILLDOWN</u>	Relationship to the drill down non-persistent object	null	UNDEFINED
LOCATIONS	<u>LOCATIONS</u>	Relationship to the Locations table, used to find all locations for a given warranty asset. (warrantyasset.location=location.location and warrantyasset.locationsite=locations.siteid). The resulting set will contain zero or one object.	location=:location and siteid=:locationsite	UNDEFINED
VIEWCONTINPUT	<u>VIEWCONTINPUT</u>	Relationship to the non-persistent ViewContInput table. (No where clause). The resulting set will contain zero objects. Note: This relationship is used only for the Asset application, displays all contracts that cover this asset and its parents.	null	UNDEFINED
VIEWWOPMS	<u>VIEWWOPMS</u>	Relationship from the WARRANTYASSET to the non-persistent VIEWWOPMS table. (No where clause.) The resulting set will contain zero objects. This relationship is used when the View Work Details dialog is launched from a location or asset field	null	UNDEFINED

MAXIMO INCOMING RELATIONSHIPS

Name	Source	Remarks	Where Clause	Cardinality
WARRANTYASSET	<u>WARRANTYVIEW</u>	Relationship to the WarrantyAsset table, used to find the WarrantyAsset records for a given Warranty Contract. (warrantyview.contractnum=warrantyasset.contractnum and warrantyview.revisionnum=warrantyasset.revisionnum and warrantyview.orgid=warrantyasset.orgid). The resulting set will contain zero or more objects.	contractnum=:contractnum and revisionnum=:revisionnum and orgid=:orgid	UNDEFINED