



***Exor Corporation Limited***



***Maintenance Manager  
Installation and Upgrade Guide  
V 4.0.2.0***



***The Global Leader in  
Infrastructure Asset Management***



# CONTENTS

---

Purpose.....	3
Products Covered by This Guide.....	3
Pre-Requisites to Installation/Upgrade .....	4
Setup.....	5
Before you Start .....	6
Typical Problems That You May Encounter.....	7
Installation of Maintenance Manager .....	8
Upgrade of Maintenance Manager .....	9
Post Install/Upgrade Tasks.....	10

## CHAPTER

## 1

# Introduction

## Purpose

This guide covers steps involved in installing/upgrading the components for Maintenance Manager.

Install/upgrade is split into two distinct stages

- Stage 1 – Installation of the Software files
- Stage 2 – Install/Upgrade of the Server

**Important:**

This product will require installing/upgrading after Network Manager.

## Products Covered by This Guide

Table 1 lists the relevant products that are covered by this guide.

Product	Install	Upgrade From
		4.0.1.0
Maintenance Manager	✓	✓

**Table 1: List of products covered by this guide**

---

## Pre-Requisites to Installation/Upgrade

Before attempting to install or upgrade, you should ensure that;

- **the appropriate software components are installed and are compatible with the exor certification matrix. The certification matrix can be downloaded from the Client area of the [exor website](#).**
- **all users are disconnected from the system**
- **the highways listener processes are not running**
- **a database export of the owner of Highways owner has been taken.**

you may also want to consider copying the current **<exor\_base>** directory and sub-directory structure and contents to a new area. This is so that these previous versions are available for reference or comparison with the new ones which will overwrite them otherwise.

CHAPTER

# 2

## Installation of the Maintenance Manager Software files

---

### Setup

To install the software components for Maintenance Manager execute the **setup\_maintenance\_manager\_4020.exe** and follow the on-screen prompts.

When the wizard completes, the necessary client and server software files will have been installed.

**Notes:**

A password is required to be entered during this process. If you are not sure of the password contact [support@exorcorp.com](mailto:support@exorcorp.com).

**Important:**

All exor applications that you install must go into the same destination – what is often referred to as **<exor\_base>**.

To support different roll-out models, you can decide to just install Client or Server or both sets of components into the **<exor\_base>**.

## Maintenance Manager Server Install/Upgrade

This chapter provides details of steps involved in installing/upgrading the server components for Maintenance Manager.

**Important:**

This product will require installing/upgrading after Network Manager.

---

### Before you Start

Before proceeding please ensure that the pre-requisites mentioned in [Chapter 1](#) of this document are met.

Also please be aware of the following;

Where instructed to change to a directory before running a script, it is assumed that you are running SQL\*PLUS from a DOS Command prompt.

If you are running SQL\*PLUS in windows you should set the 'start in' directory of the SQL\*PLUS shortcut to simulate the change of directory.

**If you do not run SQL\*PLUS from the directory stated in each step of the guide, the installation will fail.**

Also, whilst following the instructions in this section you will be required to know the location of **<exor\_base>**. You may recall that whilst undertaking the tasks in Chapter 2 you will have installed software into the location referred to as **<exor\_base>**, for example, C:\EXOR.

---

## Typical Problems That You May Encounter

It is possible that, when you are running some of the upgrade scripts, errors may be reported saying that objects already exist in the database or that columns already exist on tables. These errors can generally be ignored. If you are in any doubt, please contact the Exor support desk for guidance.

The upgrade procedures will also attempt to install database roles in the highways owner maiont that are necessary for the system to operate correctly. You may find that errors are produced when running the upgrade scripts to the effect that the role names being created are already used by existing roles or users. These errors can be ignored as they simply mean that the roles being created already exist.

Also during install/upgrade Warning messages may appear saying that compilation errors have occurred. These warnings can be ignored, since invalid objects will be recompiled prompt later on in the install/upgrade. However it will be of concern if compilation errors still occur following the re-compilation.

---

## Installation of Maintenance Manager

To create the base data and objects for Maintenance Manager modules;

Change directory to **<exor\_base>\mailinstall**

Login to SQL\*PLUS as the highways owner on the client PC and run the following command:

```
start mai_3_inst
```

You will be prompted to enter the path of the location of your highways software. This should be name of the directory, including disk identifier and a trailing slash character, referred to as **<exor\_base>**.

For example, if you installed your highways software in a directory called EXOR on your C drive, you would enter the following when prompted.

**C:\EXOR\**

When you have supplied this value, you will be prompted to confirm that it is correct and asked whether you wish to continue.

If the value specified is not correct or does not end with a slash character, you will be given an error message and the installation script will abort. You will then need to login to SQL\*PLUS again and rerun the script.

When the script has completed, all the Maintenance Manager objects and data will have been installed.

### Checking Log File(s)

The following log files are produced in the working directory. At the end of the installation, the files can be viewed to check for any errors that could have occurred during installation.

```
mai_install_1_<date&time>.LOG  
mai_install_2_<date&time>.LOG
```

#### **Note:**

Log files should be emailed to [support@exorcorp.com](mailto:support@exorcorp.com) to allow exor support staff to verify the install has been successful.



---

## Upgrade of Maintenance Manager

**This section describes the steps necessary to upgrade Maintenance Manager to 4.0.2.0**

To upgrade the base data and objects for the Maintenance Manager modules;

Change directory to **<exor\_base>\mailinstall**

Login to SQL\*PLUS as the highways owner on the client PC

The same script is used to upgrade from either of the previous versions shown in [the table in chapter 1](#). Run the following command

```
start mai4010_mai4020.sql
```

You will be prompted to enter the path of the location of your highways software. This should be name of the directory, including disk identifier and a trailing slash character, referred to as **<exor\_base>**.

For example, if you installed your highways software in a directory called EXOR on your C drive, you would enter the following when prompted.

**C:\EXOR\**

When you have supplied this value, you will be prompted to confirm that it is correct and asked whether you wish to continue.

If the value specified is not correct or does not end with a slash character, you will be given an error message and the installation script will abort. You will then need to login to SQL\*PLUS again and rerun the script.

When the script has completed, all the Maintenance Manager objects and data will have been upgraded.

## Checking Log File(s)

The following log files are produced in the working directory. At the end of the upgrade, they can be viewed to check for any errors that could have occurred during the upgrade process.

```
mai4010_mai4020_1_<date&time>.LOG  
mai4010_mai4020_2_<date&time>.LOG
```

Log files should be emailed to [support@exorcorp.com](mailto:support@exorcorp.com) to allow exor support staff to verify the upgrade has been successful.

---

## Post Install/Upgrade Tasks

### exor\_version.txt

Before installing Maintenance Manager you must check the file exor\_version.txt.

This file is referenced in Windows Registry setting 'EXOR\_VERSION' and by default can be located in the <exor\_base>\bin directory.


Ensure that the entry for Maintenance Manager is set accordingly;

MAI=4.0.2.0

### Product Licencing

Following first time installation you must licence the product for use.

To do this start highways by exor and invoke module HIG1890 from the Fastpath menu.



For further details please refer to the ***“General System Admin”*** document

### **Additional Configuration**

Consult the documentation that maiompanies this release for details of any additional configuration that may be required following an install/upgrade.

For example, to obtain details of product options, and for details of new product features/amendments.

### **Important:**

It is highly recommended that you do this before attempting to use the application.

### **Spatial Configuration**

Specific information regarding the registration of spatial layers can be found in the ***“Locator and Web Mapping”*** document.