

1. PING : Menguji kemampuan komputer dalam mencapai atau menghubungi komputer yang ditentukan.

```
C:\Users\acer>ping

Usage: ping [-t] [-a] [-n count] [-l size] [-f] [-i TTL] [-v TOS]
           [-r count] [-s count] [[-j host-list] ! [-k host-list]]
           [-w timeout] [-R] [-S srcaddr] [-4] [-6] target_name

Options:
  -t           Ping the specified host until stopped.
               To see statistics and continue - type Control-Break;
               To stop - type Control-C.
  -a           Resolve addresses to hostnames.
  -n count     Number of echo requests to send.
  -l size      Send buffer size.
  -f           Set Don't Fragment flag in packet (IPv4-only).
  -i TTL       Time To Live.
  -v TOS       Type Of Service (IPv4-only. This setting has been deprecated
               and has no effect on the type of service field in the IP Head
er).
  -r count     Record route for count hops (IPv4-only).
  -s count     Timestamp for count hops (IPv4-only).
  -j host-list Loose source route along host-list (IPv4-only).
  -k host-list Strict source route along host-list (IPv4-only).
  -w timeout   Timeout in milliseconds to wait for each reply.
  -R           Use routing header to test reverse route also (IPv6-only).
  -S srcaddr   Source address to use.
  -4           Force using IPv4.
  -6           Force using IPv6.
```

2. DIR : Berguna untuk melihat daftar file dan sub direktori yang ada di dalam sebuah direktori.

```
C:\Users\acer>dir
Volume in drive C is System
Volume Serial Number is 8C15-E6D4

Directory of C:\Users\acer

24/07/2024  01:42    <DIR>          .
24/07/2024  01:42    <DIR>          ..
26/02/2023  21:56             6.874 -1.14-windows.xml
30/05/2024  05:56    <DIR>          .android
13/11/2023  23:37    <DIR>          .eclipse
14/01/2023  20:20             50  .j2e
02/02/2020  09:35    <DIR>          .leonflix
26/11/2022  02:58    <DIR>          .nbi
13/11/2023  05:26    <DIR>          3D Objects
05/08/2023  18:58    <DIR>          Contacts
29/06/2024  12:22    <DIR>          Desktop
29/06/2024  11:06    <DIR>          Documents
25/07/2024  01:39    <DIR>          Downloads
13/11/2023  05:26    <DIR>          Favorites
13/11/2023  05:21    <DIR>          Links
20/09/2024  02:01    <DIR>          Music
31/03/2024  01:21    <DIR>          Pictures
05/08/2023  18:59    <DIR>          Saved Games
26/11/2022  03:02    <DIR>          Searches
30/10/2019  18:40             16 skb.kc
05/08/2023  18:58    <DIR>          Videos
20/02/2024  14:14    <DIR>          workspace
               3 File(s)              6.940 bytes
               19 Dir(s)      89.022.005.248 bytes free

C:\Users\acer>expand
Microsoft (R) File Expansion Utility  Version 6.1.7600.16385
Copyright (c) Microsoft Corporation. All rights reserved.

No files specified.
```

3.SYSTEMINFO :Systeminfo adalah perintah CMD yang berguna dalam memperlihatkan informasi dari komputer yang sedang digunakan.

```
C:\Users\acer>systeminfo

Host Name:                ACER-PC
OS Name:                  Microsoft Windows 7 Ultimate
OS Version:               6.1.7601 Service Pack 1 Build 7601
OS Manufacturer:         Microsoft Corporation
OS Configuration:        Standalone Workstation
OS Build Type:             Multiprocessor Free
Registered Owner:         acer
Registered Organization:
Product ID:                00426-OEM-8992662-00497
Original Install Date:    10/03/2019, 14:34:33
System Boot Time:         07/10/2024, 17:59:11
System Manufacturer:      Acer
System Model:              Aspire E1-431
System Type:               X86-based PC
Processor(s):              1 Processor(s) Installed.
                           [01]: x64 Family 6 Model 42 Stepping 7 GenuineIntel ~
1700 Mhz
BIOS Version:              Insyde Corp. U1.17, 25/04/2012
Windows Directory:        C:\Windows
System Directory:         C:\Windows\system32
Boot Device:               \Device\HarddiskVolume1
System Locale:              in;Indonesian
Input Locale:              en-us;English (United States)
Time Zone:                 (UTC+07:00) Bangkok, Hanoi, Jakarta
Total Physical Memory:    1.878 MB
Available Physical Memory: 1.389 MB
Virtual Memory: Max Size: 3.757 MB
Virtual Memory: Available: 3.008 MB
Virtual Memory: In Use:   749 MB
Page File Location(s):    C:\pagefile.sys
Domain:                    WORKGROUP
Logon Server:              \\ACER-PC
Hotfix(s):                 2 Hotfix(s) Installed.
                           [01]: KB2999226
                           [02]: KB976902
Network Card(s):          1 NIC(s) Installed.
                           [01]: Realtek PCIe GBE Family Controller
                               Connection Name: Local Area Connection
                               Status:          Media disconnected
```

4.EXPAND :Berfungsi untuk melakukan dekompresi.

```
C:\Users\acer>expand
Microsoft (R) File Expansion Utility  Version 6.1.7600.16385
Copyright (c) Microsoft Corporation. All rights reserved.

No files specified.
```

5. ARP : Mencari tahu alamat hardware dari suatu host yang tergabung dalam sebuah jaringan LAN.

```
C:\Users\acer>arp

Displays and modifies the IP-to-Physical address translation tables used by
address resolution protocol (ARP).

ARP -s inet_addr eth_addr [if_addr]
ARP -d inet_addr [if_addr]
ARP -a [inet_addr] [-N if_addr] [-v]

-a          Displays current ARP entries by interrogating the current
            protocol data. If inet_addr is specified, the IP and Physical
            addresses for only the specified computer are displayed. If
            more than one network interface uses ARP, entries for each ARP
            table are displayed.
-g          Same as -a.
-v          Displays current ARP entries in verbose mode. All invalid
            entries and entries on the loop-back interface will be shown.
inet_addr   Specifies an internet address.
-N if_addr  Displays the ARP entries for the network interface specified
            by if_addr.
-d          Deletes the host specified by inet_addr. inet_addr may be
            wildcarded with * to delete all hosts.
-s          Adds the host and associates the Internet address inet_addr
            with the Physical address eth_addr. The Physical address is
            given as 6 hexadecimal bytes separated by hyphens. The entry
            is permanent.
eth_addr    Specifies a physical address.
if_addr     If present, this specifies the Internet address of the
            interface whose address translation table should be modified.
            If not present, the first applicable interface will be used.

Example:
> arp -s 157.55.85.212 00-aa-00-62-c6-09 .... Adds a static entry.
> arp -a                                     .... Displays the arp table.

C:\Users\acer>chage
'chage' is not recognized as an internal or external command,
operable program or batch file.
```