

How to use DERO RPC-Bridge

Requirements:

- Your computer
- Internet connection
- a DERO wallet
- Chrome browser

DERO PROJECT
STARGATE RC2

How to use DERO RPC-Bridge

Agenda:

1. Open your wallet (CLI mode)
 2. Install Google Chrome Extension
- Connect the extension to your wallet.

How to use DERO RPC-Bridge

1. Open your wallet (CLI mode)

Follow the steps described here:

https://docs.dero.io/rtd_pages/basic_howtoswap.html#opening-wallet

Command line to launch your wallet is :

`.\dero-wallet-cli- PLATFORM --remote --rpc-server --rpc-login username:password`

Where PLATFORM is your Operating system (Darwin, linux, arm....)

Security warning: choose a *strong and complex* password to connect to your wallet)

DERO PROJECT
STARGATE RC2


How to use DERO RPC-Bridge

2. Install Google Chrome Extension

Open Google Chrome and go to


<https://chrome.google.com/webstore/detail/dero-rpc-bridge/nmofcfcaegdplgbjnadipebgfbodplpd>

Click “Add to Chrome”




How to use DERO RPC-Bridge

Click "Add extension"



DERO RPC-bridge is now installed



How to use DERO RPC-Bridge

3. Configure RPC-Bridge

a. Connect to a public RPC daemon

(<http://185.132.176.174:10102> or <https://dero-node.mysrv.cloud/>)


Click "SET"

b. Connect to your wallet:

<http://localhost:10103>

c. Type your username
and password
(see page 3 for your password)

d. Click "SET"



The screenshot shows the 'DERO RPC Bridge' configuration window. It has two main sections: 'Daemon RPC' and 'Wallet RPC'. Each section has a text input field for the RPC URL, a 'SET' button, a status indicator (green dot for 'Connected'), and a 'Node Height' or 'Balance' display. The 'Wallet RPC' section also includes 'RPC Login' fields for 'User' and 'Password'. Orange lines from the text instructions point to the 'SET' buttons and the input fields.

DERO RPC Bridge	
Daemon RPC	
<input type="text" value="http://185.132.176.174:10102"/>	SET
Connected	
Node Height	314372
Wallet RPC	
<input type="text" value="http://localhost:10103"/>	SET
Connected	
Balance	0.99389 DERO
RPC Login	
User	<input type="text" value="username"/>
Password	<input type="password" value="*****"/>

How to use DERO RPC-Bridge

Basic flow description

