

Printer (Konica Minolta C658 PS) Access on Macs

Updated August 2019

1. Download and install the proper driver here:

<https://onyxweb.mykonicaminolta.com/OneStopProductSupport?appMode=public&productId=1979&categoryId=1&subCategoryId=ft0>

Note that you should know which version OS you're using (go to apple icon, and "about his mac" and note your version. Select a driver based on this.) Open the downloaded zip file and proceed to install the driver. Use the Letter pkg rather than the A4.

2. Go to System Preferences > Printers & Scanners. On the left side of the window, click the plus sign.
3. Go to the IP tab and enter this address: 129.105.12.142

Some of the other fields will begin to auto-populate. Under "Name" you can re-name the printer whatever you want.

4. Under "Use," go to "select software" and select "Konica Minolta C658 PS"
5. Click Add. A window will pop up that says "Setting up 'printer name...' and will ask you to make sure your printer's options are accurate.

Function Version: Version4.0 or more

Paper Source Unit: LU-302

Finisher: FS-537


Punch Unit: None

Z-Fold Unit: None

Port Inserter: None

Security Document Setting: Release Secure Print


Tick only "Hard Disk" and scroll down if necessary, to uncheck any other boxes. Click Okay.



The screenshot shows a dark-themed configuration window for a printer. It contains several settings, each with a label and a dropdown menu. The settings are: Function Version (Version4.0 or more), Paper Source Unit (LU-302), Finisher (FS-537), Punch Unit (None), Z-Fold Unit (None), Post Inserter (None), and Security Document Setting (Release Secure Print). Below these settings, there are three checkboxes: 'Hard Disk' (checked), 'Secure Print Only' (unchecked), and 'Allow Public User' (unchecked).

Function Version:	Version4.0 or more
Paper Source Unit:	LU-302
Finisher:	FS-537
Punch Unit:	None
Z-Fold Unit:	None
Post Inserter:	None
Security Document Setting:	Release Secure Print
<input checked="" type="checkbox"/> Hard Disk	
<input type="checkbox"/> Secure Print Only	
<input type="checkbox"/> Allow Public User	

6. Every application will be a little different, but when you print in an application for the first time, you'll have to look for settings in "Output Method." You can usually find this in a drop down menu. This may be on the first printing prompt you see, or may be found in advanced settings, or if from the web "print using system dialog"



Tick "Account Track." A window will pop up. You can enter anything you want for your name. Your password is your entire student ID number (NOT NetID).

- Tick Save Settings and click OK. Once you leave that "Account Track" window, go up to the "Presets" and select from the dropdown "Save Current Settings as Preset."

Troubleshooting:

- Check that you clicked "account track," rather than "user authentication"
- Check that you entered your student ID number, NOT your NetID. Student ID number is found on your WildCard and is usually about 7 digits long. NetIDs usually start with 3 letters followed by 3 or 4 numbers

Examples:

- Student ID: 555555 or 1234567
- NetID: abc555