

Table Of Contents

Table Of Contents 1

Task: Determine which runlevel my system is currently in 2

Task: Change runlevel 2

[Home](#) > [Faq](#) > [Linux](#)

Linux define the runlevel and determine which runlevel my system is currently in

Posted by [Vivek Gite](#) <vivek@nixcraft.com>

Q. How to define the Linux system runlevel and how do I determine which runlevel my system is currently in?

A. You need to use runlevel command to find the current and previous system runlevel. Usaully 0-6 runlevel are used by all Linux distributions:

- => 0 : Halt system
- => 1 : Take system to single-user mode (good for Linux system maintenance)
- => 2 : User defined or distribution like Debian use it
- => 3 : Full multi-user mode (text mode login)
- => 4 : Not used/user-defined
- => 5 : Full multi-user GUI mode login
- => 6 : Reboot system

Please note that runlevels 0, 1, and 6 are reserved. Runlevel 0 is used to halt the system, runlevel 6 is used to reboot the system, and runlevel 1 is used to get the system down into single user mode.

Task: Determine which runlevel my system is currently in

Type runlevel command:

```
$ runlevel
```

Output:

```
N 3
```

runlevel command reads the system utmp file (typically /var/run/utmp) to locate the runlevel record, and then prints the previous and current system runlevel on its standard output, separated by a single space. If there is no previous system runlevel, the letter N will be printed instead.

Task: Change runlevel

Use init command to change the runlevel. For example runlevel 1 is used to get the system down into single user mode:

```
# init 1
```

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our [daily email](#) newsletter or [weekly newsletter](#) to make sure you don't miss a single tip/tricks. Alternatively, subscribe via [RSS/XML](#) feed.

Article printed from Frequently Asked Questions About Linux / UNIX: <http://www.cyberciti.biz/faq/>

URL to article: <http://www.cyberciti.biz/faq/linux-define-the-runlevel-and-determine-which-runlevel-my-system-is-currently-in/>
