

Table Of Contents

Table Of Contents 1

Install pdftotext under RedHat / RHEL / Fedora / CentOS Linux 2

 pdftotext syntax 2

 How do I convert a pdf to text? Convert a pdf file called hp-manual.pdf to hp-manual.txt, enter: \$ pdftotext hp-manual.pdf hp-manual.txt Specifies 2

Further readings: 2

[Home](#) > [Faq](#) > [BASH Shell](#)

pdftotext: Linux / UNIX Convert a PDF File To Text Format

Posted by [Vivek Gite](#) <vivek@nixcraft.com>

Question: I've downloaded configuration file in a PDF format. I do not have GUI installed on remote Linux / UNIX server. How do I **convert a PDF (Portable Document Format) file to a text format using command line** so that I can view file over remote ssh session?

Answer: Use pdftotext utility to convert Portable Document Format (PDF) files to plain text. It reads the PDF file, and writes a text file. If text file is not specified, pdftotext converts file.pdf to file.txt. If text-file is -, the text is sent to stdout.



[1]

Install pdftotext under RedHat / RHEL / Fedora / CentOS Linux

pdftotext is installed using poppler-utils package under various Linux distributions:

```
# yum install poppler-utils
```

OR use the following under [Debian / Ubuntu Linux](#)

```
$ sudo apt-get install poppler-utils
```

pdftotext syntax

```
pdftotext {PDF-file} {text-file}
```

How do I convert a pdf to text?

Convert a pdf file called hp-manual.pdf to hp-manual.txt, enter:

```
$ pdftotext hp-manual.pdf hp-manual.txt
```

Specifies the first page 5 and last page 10 (select 5 to 10 pages) to convert, enter:

```
$ pdftotext -f 5 -l 10 hp-manual.pdf hp-manual.txt
```

Convert a pdf file protected and encrypted by owner password:

```
$ pdftotext -opw 'password' hp-manual.pdf hp-manual.txt
```

Convert a pdf file protected and encrypted by user password:

```
$ pdftotext -upw 'password' hp-manual.pdf hp-manual.txt
```

Sets the end-of-line convention to use for text output. You can set it to unix, dos or mac. For UNIX / Linux oses, enter:

```
$ pdftotext -eol unix hp-manual.pdf hp-manual.txt
```

Further readings:

- [man page pdftotext](#)

4000+ howtos and counting! Want to read more Linux / UNIX howtos, tips and tricks? Subscribe to our [daily email](#) newsletter or [weekly newsletter](#) to make sure you don't miss a single tip/tricks. Alternatively, subscribe via [RSS/XML](#) feed.

Article printed from Frequently Asked Questions About Linux / UNIX: <http://www.cyberciti.biz/faq/>

URL to article: <http://www.cyberciti.biz/faq/converter-pdf-files-to-text-format-command/>

URLs in this post:

[1] Image: <http://www.cyberciti.biz/faq/category/linux/>

Copyright © 2006-2010 [nixCraft](#). All rights reserved. This print / pdf version is for personal non-commercial use only. More details <http://www.cyberciti.biz/tips/copyright>.