

.MODEL SMALL

.CODE

```
MOV AH,2CH
INT 21H                ; ch cl dh
                       ;14:24:36
MOV AL,CH              ; AAM-14=0104
AAM                    ;      3030
MOV BX,AX              ;      ax=3134
CALL DISP              ;      mov dl,ah
MOV DL,':'              ;      mov ah,02h
MOV AH,02H              ;      int 21h
INT 21H
```

```
MOV AL,CL
AAM
MOV BX,AX
CALL DISP
MOV DL,':'
MOV AH,02H
INT 21H
```

```
MOV AL,DH
AAM
MOV BX,AX
CALL DISP
```

```
MOV AH,4CH
INT 21H
```

DISP PROC NEAR

```
MOV DL,BH              ;BX=0104
ADD DL,30H              ; 31
MOV AH,02H ;display character
INT 21H
MOV DL,BL
ADD DL,30H
mov ah,02h
INT 21H
RET
DISP ENDP
END
```

```

File Edit View Search Run Watch Options Calls Help
local
source1 CS:IP (ACTIVE)
052A:002B B44C      MOV     AH,4C
052A:002D CD21      INT     21
052A:002F 8AD7      MOV     DL,BH
052A:0031 80C230     ADD     DL,30
052A:0034 B402      MOV     AH,02
052A:0036 CD21      INT     21
052A:0038 8AD3      MOV     DL,BL
052A:003A 80C230     ADD     DL,30
052A:003D B402      MOV     AH,02
052A:003F CD21      INT     21
052A:0041 C3        RET
052A:0042 8E06E401    MOV     ES,Word Ptr [01E4]
052A:0046 268B162C00  MOV     DX,Word Ptr ES:[002C]
052A:004B E87B02      CALL    02C9
052A:004E B792      MOV     BH,92
052A:0050 B9FF7F      MOV     CX,7FFF
AX = 4C36
BX = 0406
CX = 0D3B
DX = 2E36
SP = 0000
BP = 0000
SI = 0000
DI = 0000
DS = 051A
ES = 051A
SS = 0529
CS = 052A
IP = 002F
FL = 0206
NU UP EI PL
NZ NA PE NC
command
051A:0000 CD 20 FF 9F 00 EA FF FF-AD DE 6C 02 CD 03 32 03 . ...
051A:0010 CD 03 4B 0A CD 03 FF 04-FF FF FF FF FF FF FF ..K..
>

```


C:\MASM>link TIMEDISP;;

Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.

LINK : warning L4021: no stack segment

C:\MASM>cv TIMEDISP

13:59:46

Type EXIT to return to CodeView

Welcome to DOSBox v0.74

For a short introduction for new users type: **INTRO**

For supported shell commands type: **HELP**

To adjust the emulated CPU speed, use **ctrl-F11** and **ctrl-F12**.

To activate the keymapper **ctrl-F1**.

For more information read the **README** file in the DOSBox directory

HAVE FUN!

The DOSBox Team <http://www.dosbox.com>

C:\MASM>_