

北京尚观 Linux 系统网络安装说明

安装服务器功能：

1. 在线临时启动 Linux 系统
2. 自动安装 RHEL5/RHEL6 系统
3. 手动安装 RHEL5/RHEL6 系统


安装提示：


1. 不同版本安装源路径 <仅手动安装需要>
RHEL5.8 x86_32 ftp://172.16.8.100/rhel5.8_32
RHEL5.8 x86_64 ftp://172.16.8.100/rhel5.8
RHEL6.4 x86_64 ftp://172.16.8.100/rhel6.4
2. 安装时，尽量使用集成网卡

详细安装步骤：


一、主机 BIOS 中开启网络引导功能，不同主机 BIOS 版本不同，开启方法均不相同


BIOS 版本 1:





BIOS 版本 2:





二、主机启动过程中提示按 **F8** 或 **F12** 选择从网络启动，将出来如下界面

提示：不需要在 BIOS 中永久设置设备的启动顺序，只需在开机过程中按提示选择 **F8** 或 **F12** 键临时从网络启动即可。



三、在线启动系统

适合临时快速启动 Linux 系统，不会影响当前硬盘中的任何数据，该 Live 系统仅会在内存中运行。该系统中已经预装了 VNC 软件，可直接使用。



四、手动安装 REHL6

Welcome to the Uploading system installation services!

Boot RHEL 6.5 Live
Install RHEL 5.8 x86_32 <Automatic>
Install RHEL 5.8 x86_64 <Automatic>
Install RHEL 6.4 x86_64 <Automatic>
Install RHEL 5.8 x86_32 <Manual>
Install RHEL 5.8 x86_64 <Manual>
Install RHEL 6.4 x86_64 <Manual>
Boot from local drive
Install system with basic video driver
Rescue installed system
Memory test

Press [Tab] to edit options

**RED HAT®
ENTERPRISE LINUX® 6**



Copyright © 2003-2010 Red Hat, Inc. and others. All rights reserved.

Welcome to Red Hat Enterprise Linux for x86_64

Choose a Language

What language would you like to use during the installation process?

Catalan
Chinese(Simplified)
Chinese(Traditional)
Croatian
Czech
Danish
Dutch
English

OK

<Tab>/<Alt-Tab> between elements | <Space> selects | <F12> next screen

Welcome to Red Hat Enterprise Linux for x86_64

Keyboard Type

What type of keyboard do you have?

- slovene
- sr-cy
- sr-latin
- sv-latin1
- trq
- ua-utf
- uk
- us**

OK Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

Welcome to Red Hat Enterprise Linux for x86_64



Installation Method

What type of media contains the installation image?


- Local CD/DVD
- Hard drive
- NFS directory
- URL**

OK Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen



五、手动安装 RHEL5



Welcome to Red Hat Enterprise Linux Server

Keyboard Type

What type of keyboard do you have?

- sg-latin1
- sk-qwerty
- slovene
- sv-latin1
- trq
- ua-utf
- uk
- us**

OK Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

Welcome to Red Hat Enterprise Linux Server

Installation Method

What type of media contains the packages to be installed?

- Local CDROM
- Hard drive
- NFS image
- FTP**
- HTTP

OK Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

Welcome to Red Hat Enterprise Linux Server

Configure TCP/IP

[*] Enable IPv4 support

(*) Dynamic IP configuration (DHCP)

() Manual configuration

[] Enable IPv6 support

(*) Automatic neighbor discovery (RFC 2461)

() Dynamic IP configuration (DHCP)

() Manual configuration

OKBack

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

Welcome to Red Hat Enterprise Linux Server

Configure TCP/IP

Missing Nameserver

Your IP address request returned configuration information,
but it did not include a nameserver address. If you do not
have this information, you can leave the field blank and
the install will continue.

Nameserver IP

OK直接回车Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

Welcome to Red Hat Enterprise Linux Server

FTP Setup

Please enter the following information:

- o the name or IP number of your FTP server
- o the directory on that server containing Red Hat Enterprise Linux Server for your architecture

FTP site name: 172.16.8.100

Red Hat Enterprise Linux Server directory: rhel5.8

[] Use non-anonymous ftp

OK Back

<Tab>/<Alt-Tab> between elements ; <Space> selects ; <F12> next screen

