

Using GitLab

GitLab is a DevOps tool developed by GitLab. You can clone projects from GitLab servers and use [Git](#) to manage your local and remote repositories.


To enable the experimental GitLab plugin, select **Help > About Plugins > Version Control > GitLab**. Then select **Restart Now** to restart Qt Creator and load the plugin.

To use GitLab, you must create a connection to the GitLab server and clone the projects you want to work on. You can also link previously cloned projects to GitLab in the project settings. This enables you to receive event notifications in the [Version Control](#) pane.

Connecting to GitLab Servers


To connect to a GitLab server, you need to specify the server host name and port number, as well as an access token that you create in GitLab for Qt Creator. The permission scope of the token must be at least `read_api` or `api`.


To specify connections to GitLab servers, select **Edit > Preferences > Version Control > GitLab**:



To add GitLab servers:

1. Select **Add** to open the **Add Server** dialog:





2. In **Host**, enter the host name of the GitLab server.
3. In **Description**, enter a free-form text that is displayed in the GitLab settings of a linked project.
4. In **Access token**, enter the access token you created for Qt Creator in the GitLab server, in **Preferences > Access Tokens**.
5. In **Port**, enter a port number.
6. Deselect the **HTTPS** check box to use an HTTP connection instead of a secure connection.
7. Select **Add** to create the connection.

In the **GitLab** tab, **curl** displays the path to the **curl** tool used for HTTP connections. You can specify another path to use another instance of the tool than the one found by Qt Creator.

To edit the selected connection, select **Edit**.


To remove the selected connection, select **Remove**.

Cloning Projects

You can clone projects from the connected GitLab servers. Qt Creator reads your user name and ID from the access token and displays the available projects in each server. You can search for a particular project or browse projects in the list.


To clone projects from GitLab:

1. Select **Tools > GitLab** to view a list of connected GitLab servers and available projects in each server:



2. In **Remote**, select a GitLab server.

3. In **Projects**, select the project to clone.



5. In **Repository**, specify the URL of the repository.
6. In **Path**, specify the path where to clone the repository.
7. In **Directory**, specify the name of the directory for the cloned repository.
8. Select the **Recursive** check box to also clone submodules of the repository.
9. Select **Clone** to clone the project to the specified directory.


Qt Creator automatically opens the project. If the cloned project has several project files (such as CMakeList.txt, .pro, and .qbs), Qt Creator prompts you to select the one to open. If it does not contain a project file that Qt Creator can open, select **File > New Project > Import Project > Import Existing Project** to import the project as a generic project. For more information, see [Using Project Wizards](#).

Linking Projects with GitLab

Link a project with a GitLab token to receive notifications on events, such as merge requests, issues, or comments, in the **Version Control** pane. The information is fetched every 15 minutes. Only events that occurred after the last time you logged into GitLab are displayed when you open the project for the first time. Subsequently, events that occurred after the last successful fetch are listed.

To link with GitLab:

1. In the **Projects** mode, select **GitLab** to view the GitLab settings for the currently active project:



2. In **Host**, select the URL of the GitLab server.
3. In **Linked GitLab configuration**, select the GitLab server settings to use.
4. Select **Link with GitLab** to receive event notifications in the **Version Control** pane.

Connection.

To stop the reception of event notifications, select **Unlink from GitLab**.

[< Using Git](#)[Using Mercurial >](#)

© 2022 The Qt Company Ltd. Documentation contributions included herein are the copyrights of their respective owners. The documentation provided herein is licensed under the terms of the [GNU Free Documentation License version 1.3](#) as published by the Free Software Foundation. Qt and respective logos are trademarks of The Qt Company Ltd in Finland and/or other countries worldwide. All other trademarks are property of their respective owners.

[Contact Us](#)

Company

- [About Us](#)
- [Investors](#)
- [Newsroom](#)
- [Careers](#)
- [Office Locations](#)

Support

- [Support Services](#)
- [Professional Services](#)
- [Partners](#)
- [Training](#)

Community

- [Contribute to Qt](#)
- [Forum](#)
- [Wiki](#)
- [Downloads](#)
- [Marketplace](#)

Licensing

- [Terms & Conditions](#)
- [Open Source](#)
- [FAQ](#)

For Customers

- [Support Center](#)
- [Downloads](#)
- [Qt Login](#)
- [Contact Us](#)
- [Customer Success](#)

