

All-In-One Epic-Cash Mining Package



Package requirements:

1. Windows 8/10 64bit

Minimum mining requirements:

1. CPU: 2 cores
2. RAM: 2GB for each core
3. GPU: 3GB VRAM
4. HDD: 2GB space

Package content:

1. epic.exe from epic.tech/downloads
2. epic-wallet.exe from epic.tech/downloads
3. epic-miner-cpu.exe from epic.tech/downloads
4. epic-miner-gpu.exe from epic.tech/downloads
5. epic-tools.exe from github.com/EpicCash
6. pre-installed blockchain data updated 05/08/2021

How to use:


1. Unpack Start mining BETA.zip file (can be anywhere)
2. Run Start mining BETA.exe file

Current limitations:

- Some antiviruses will throw warnings with this package as it is related to mining and written in Python - a popular language for hackers ;)
- Works only with stock epic-miner.exe
- CPU mining can be manually improved
- No Cuckoo/ASIC algorithm available

Beginners guide:

When running for the first time user have to create wallet protected by password




To start mining please create wallet

Password

Repeat password

Create wallet

After wallet creation there is 24 word seed phrase shown - THIS IS THE ONLY TIME AND NEEDS TO BE SAVED SOMEWHERE ELSE IDEALLY NON DIGITAL FORM. This seed phrase is the key to access and manage the user's wallet, keep it safe.



Now you have full access to that wallet :D

Now user have access to basic mining dashboard



Once mining is started there will be a couple CMD windows running on the machine.

1. Epic-Cash Server:

```
C:\Users\IOPDG\Desktop\stuff\mining-manager\epic-tools-beta\epic-server\epic.exe

Epic Version 2.15.0

Basic Status
Peers and Sync
Mining
Version Info

Current Status: Downloading headers: 99%, step 1/4
Connected Peers: 16

Header Tip Hash: beb28333929c...
Header Chain Height: 1033580
Header Cumulative Difficulty: Cuckatoo: 839542905765, ProgPow: 613110992712223827, RandomX: 619821251689131

Chain Tip Hash: b9a27bca61db...
Chain Height: 1033100
Chain Cumulative Difficulty: Cuckatoo: 837349644323, ProgPow: 612851154164032893, RandomX: 619317482922664

Tab/Arrow : Cycle
Enter : Select
Esc : Back
Q : Quit
```

If 'current status' is different than 'Running' it means server is synchronizing with blockchain

2. CPU and/or GPU mining software:

```
C:\Users\IOPDG\Desktop\stuff\mining-manager\epic-tools-beta\cpu-miner\epic-miner-cpu.exe

Epic Miner Version 2.3.1

Mining
Version Info

Connection Status: Starting
Current Network Difficulty:
Network Needed Algorithm:
Mining Status: Waiting for server

Last Message Sent: None
Last Message Received: None

Plugin [^] ? Device ID ? Mining Devices [ ] ? Status [ ? HPS [ ]

Tab/Arrow : Cycle
Enter : Select
Q : Quit
```

Troubleshooting

24h Telegram support at: <https://t.me/epiccashhelpdesk>

- epic.exe window is black, not working

Go to `epic-server.log` file in `epic-tools-beta\epic-server\`
Look for error feedback at the end of the file and share with us on telegram

- epic-miner.exe is not connecting or not working

Go to `epic-miner.log` file in `epic-tools-beta\epic-miner-cpu\`
or `epic-tools-beta\epic-miner-gpu` directory
Look for error feedback at the end of the file and share with us on telegram

- epic-wallet.exe is not working, listener is offline

Go to `epic-wallet.log` file in `epic-tools-beta\epic-wallet`
Look for error feedback at the end of the file and share with us on telegram