


Modul 8

Nama : Bagas Ivaniajie

NIM : L200170181

Kelas : D

Kegiatan 1. Konfigurasi Access List



Konfigurasi alamat IP pada Switch1.

```
Switch>enable
Switch#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int vlan 1
Switch(config-if)#ip address 192.168.110.250 255.255.255.0
Switch(config-if)#no shutdown

Switch(config-if)#
%LINK-5-CHANGED: Interface Vlan1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up
```

Konfigurasi alamat IP pada Switch2.

```
Switch>enable
Switch#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#int vlan 1
Switch(config-if)#ip address 192.168.120.250 255.255.255.0
Switch(config-if)#no shutdown


Switch(config-if)#
%LINK-5-CHANGED: Interface Vlan1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Vlan1, changed state to up
```

Konfigurasi alamat IP, Subnet Mask, dan Default Gateway pada masing-masing PC.
PC 1

The screenshot shows the configuration window for PC1. The 'Config' tab is active, and the 'Desktop' sub-tab is selected. Under the 'DHCP' section, the 'Static' radio button is selected. The 'IP Address' field is set to 192.168.110.3, the 'Subnet Mask' is 255.255.255.0, and the 'Default Gateway' is 192.168.110.254. The 'DNS Server' field is set to 0.0.0.0. In the 'IPv6 Configuration' section, the 'Static' radio button is selected. The 'IPv6 Address' field is empty, and the 'Link Local Address' is set to FE80:260:2FFF:FE59:CD38. The 'IPv6 Gateway' and 'IPv6 DNS Server' fields are empty. In the '802.1X' section, the 'Use 802.1X Security' checkbox is unchecked. The 'Authentication' dropdown menu is set to 'none'. The 'Username' and 'Password' fields are empty. A 'Top' button is located at the bottom left of the window.

PC 2



The screenshot shows the configuration window for PC2. The 'Config' tab is selected, and the 'Static' radio button is chosen for IP configuration. The IP Address is 192.168.110.4, Subnet Mask is 255.255.255.0, Default Gateway is 192.168.110.254, and DNS Server is 0.0.0.0. For IPv6, the 'Static' radio button is also selected, with a Link Local Address of FE80:200:47FF:FED1:3253. The 802.1X section shows 'Use 802.1X Security' is unchecked, and the Authentication dropdown is set to 'MD5'. A 'Top' button is located at the bottom left.

PC2

Physical Config Desktop Programming Attributes

☐ DHCP ☒ Static

IP Address: 192.168.110.4

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.110.254

DNS Server: 0.0.0.0

IPv6 Configuration

☐ DHCP ☐ Auto Config ☒ Static

IPv6 Address: /

Link Local Address: FE80:200:47FF:FED1:3253

IPv6 Gateway:

IPv6 DNS Server:

802.1X

☐ Use 802.1X Security


Authentication: MD5

Username:

Password:

☐ Top

PC 3



The screenshot shows the configuration window for PC3. The 'Config' tab is selected, and the 'Static' radio button is chosen for IP configuration. The IP Address is 192.168.120.3, Subnet Mask is 255.255.255.0, Default Gateway is 192.168.120.254, and DNS Server is 0.0.0.0. For IPv6, the 'Static' radio button is also selected, with a Link Local Address of FE80:20C:CFFF:FE11:8597. The 802.1X section shows 'Use 802.1X Security' is unchecked, and the Authentication dropdown is set to 'MD5'. A 'Top' button is located at the bottom left.

PC3

Physical Config Desktop Programming Attributes

☐ DHCP ☒ Static

IP Address: 192.168.120.3

Subnet Mask: 255.255.255.0

Default Gateway: 192.168.120.254

DNS Server: 0.0.0.0

IPv6 Configuration

☐ DHCP ☐ Auto Config ☒ Static

IPv6 Address: /

Link Local Address: FE80:20C:CFFF:FE11:8597

IPv6 Gateway:

IPv6 DNS Server:

802.1X

☐ Use 802.1X Security

Authentication: MD5

Username:

Password:

☐ Top

PC 4

The screenshot shows the configuration window for PC4. The 'Config' tab is selected. Under the 'Static' radio button, the IP Address is 192.168.120.4, Subnet Mask is 255.255.255.0, Default Gateway is 192.168.120.254, and DNS Server is 0.0.0.0. The 'IPv6 Configuration' section has the 'Static' radio button selected, with an empty IPv6 Address field, a Link Local Address of FE80::20B:BEFF:FE56:4753, and empty fields for IPv6 Gateway and IPv6 DNS Server. The '802.1X' section has 'Use 802.1X Security' unchecked, and the 'Authentication' dropdown is set to 'MD5'. There are empty fields for Username and Password. A 'Top' button is at the bottom left.

Konfigurasi alamat IP dan Interface pada masing-masing Router.

Router 1

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#no ip address
Router(config-if)#ip address 192.168.10.1 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#ip address 192.168.110.254 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
```

Router 2

```
Router>enable
Router#
Router#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface FastEthernet0/0
Router(config-if)#ip address 192.168.10.2 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed state to up

Router(config-if)#exit
Router(config)#interface FastEthernet0/1
Router(config-if)#ip address 192.168.120.254 255.255.255.0
Router(config-if)#no shutdown
Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/1, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/1, changed state to up
```

Membuat Routing dengan Protokol RIP.

Router 1

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 192.168.110.0
Router(config-router)#network 192.168.10.0
Router(config-router)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Router 2

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#router rip
Router(config-router)#network 192.168.120.0
Router(config-router)#network 192.168.10.0
Router(config-router)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Pengecekan Table Routing pada masing-masing Router.

Router 1

```
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    192.168.10.0/24 is directly connected, FastEthernet0/0
C    192.168.110.0/24 is directly connected, FastEthernet0/1
R    192.168.120.0/24 [120/1] via 192.168.10.2, 00:00:01, FastEthernet0/0
```

Router 2

```
Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    192.168.10.0/24 is directly connected, FastEthernet0/0
R    192.168.110.0/24 [120/1] via 192.168.10.1, 00:00:11, FastEthernet0/0
C    192.168.120.0/24 is directly connected, FastEthernet0/1
```

Tes koneksi (ping) dari PC1 ke PC4.

```
C:\>ping 192.168.120.4

Pinging 192.168.120.4 with 32 bytes of data:

Reply from 192.168.120.4: bytes=32 time=2ms TTL=126
Reply from 192.168.120.4: bytes=32 time=1ms TTL=126
Reply from 192.168.120.4: bytes=32 time=1ms TTL=126
Reply from 192.168.120.4: bytes=32 time=11ms TTL=126

Ping statistics for 192.168.120.4:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 11ms, Average = 3ms
```

Access List yang mengijinkan semua host dari jaringan 192.168.120.0 dapat mengakses jaringan 192.168.100.0

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#access-list 10 permit 192.168.120.0 0.0.255.255
Router(config)#end
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Penerapan Access List pada Interface Router 1.

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/1
Router(config-if)#ip access-group 10 out
Router(config-if)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Menampilkan konfigurasi Access List pada Router 1.

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/1
Router(config-if)#ip access-group 10 out
Router(config-if)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show access-lists
Standard IP access list 10
 10 permit 192.168.0.0 0.0.255.255
Router#
```


Konfigurasi Access List pada Ethernet 1.

```
Router#show running-config
Building configuration...

Current configuration : 712 bytes
!
version 12.4
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname Router
!
!
!
!
!
!
!
ip cef
no ipv6 cef
!
!
--More-- |
```

```
spanning-tree mode pvst
!
!
!
!
!
interface FastEthernet0/0
ip address 192.168.10.1 255.255.255.0
duplex auto
speed auto
!
interface FastEthernet0/1
ip address 192.168.110.254 255.255.255.0
ip access-group 10 out
duplex auto
speed auto
!
interface Vlan1
no ip address
shutdown
!
router rip
network 192.168.10.0
--More-- |
```



```

router rip
 network 192.168.10.0
 network 192.168.110.0
 !
 ip classless
 !
 ip flow-export version 9
 !
 !
 access-list 10 permit 192.168.0.0 0.0.255.255
 !
 !
 !
 !
 !
 line con 0
 !
 line aux 0
 !
 line vty 0 4
 login
 !
 !

```

Tes koneksi dua arah antara PC3 dengan PC1.
 Dari PC1 ke PC3

```

C:\>ping 192.168.120.3

Pinging 192.168.120.3 with 32 bytes of data:

Reply from 192.168.120.3: bytes=32 time<1ms TTL=126
Reply from 192.168.120.3: bytes=32 time<1ms TTL=126
Reply from 192.168.120.3: bytes=32 time=11ms TTL=126
Reply from 192.168.120.3: bytes=32 time=13ms TTL=126

Ping statistics for 192.168.120.3:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 13ms, Average = 6ms

```

Dari PC3 ke PC1

```

Packet Tracer PC Command Line 1.0
C:\>ping 192.168.110.3

Pinging 192.168.110.3 with 32 bytes of data:

Reply from 192.168.110.3: bytes=32 time<1ms TTL=126
Reply from 192.168.110.3: bytes=32 time=24ms TTL=126
Reply from 192.168.110.3: bytes=32 time<1ms TTL=126
Reply from 192.168.110.3: bytes=32 time<1ms TTL=126

Ping statistics for 192.168.110.3:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 24ms, Average = 6ms

```

Access List pada 1 host yaitu PC4 dengan alamat IP 192.168.120.4 agar dapat mengakses jaringan 192.168.110.0

```
Router>enable
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#access-list 20 permit 192.168.120.4 0.0.0.0
Router(config)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Penerapan Access List ke interface [Ethernet 1] pada Router 1.

```
Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/1
Router(config-if)#ip access-group 20 out
Router(config-if)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console
```

Tes koneksi dari PC3 ke PC1 dan PC2.

```
C:\>ping 192.168.110.3

Pinging 192.168.110.3 with 32 bytes of data:

Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.

Ping statistics for 192.168.110.3:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),

C:\>ping 192.168.110.4

Pinging 192.168.110.4 with 32 bytes of data:

Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.
Reply from 192.168.10.1: Destination host unreachable.

Ping statistics for 192.168.110.4:
    Packets: Sent = 4, Received = 0, Lost = 4 (100% loss),
```

Tes koneksi dari PC4 ke PC1 dan PC2.

```
C:\>ping 192.168.110.3

Pinging 192.168.110.3 with 32 bytes of data:

Reply from 192.168.110.3: bytes=32 time=5ms TTL=126
Reply from 192.168.110.3: bytes=32 time=11ms TTL=126
Reply from 192.168.110.3: bytes=32 time=15ms TTL=126
Reply from 192.168.110.3: bytes=32 time=1ms TTL=126

Ping statistics for 192.168.110.3:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 15ms, Average = 7ms


C:\>ping 192.168.110.4

Pinging 192.168.110.4 with 32 bytes of data:

Reply from 192.168.110.4: bytes=32 time<1ms TTL=126
Reply from 192.168.110.4: bytes=32 time=12ms TTL=126
Reply from 192.168.110.4: bytes=32 time<1ms TTL=126
Reply from 192.168.110.4: bytes=32 time=2ms TTL=126

Ping statistics for 192.168.110.4:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 12ms, Average = 3ms
```

Kegiatan 2. Konfigurasi Extended Access List



Router1

Physical Config **CLI** Attributes

IOS Command Line Interface

```
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int fa0/1
Router(config-if)#ip access-group 20 out
Router(config-if)#^Z
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#conf term
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#access-list 100 permit tcp 192.168.120.0 0.0.0.255 192.168.110.3
0.0.0.0 eq any
^
% Invalid input detected at '^' marker.

Router(config)#access-list 100 permit tcp 192.168.120.0 0.0.0.255 192.168.110.3
0.0.0.0 eq telnet
Router(config)#int fa0/1
Router(config-if)#ip access-group 100 in
Router(config-if)#exit
Router(config)#
```

Ctrl+F6 to exit CLI focus

Copy Paste

☐ Top