

Mod. Pool Z_UPDATE_EXAMPLE Active

```
1  * &-----*
2  * & Module Pool      Z_UPDATE_EXAMPLE
3  * &-----*
4  * &
5  * &-----*
6
7  INCLUDE Z_UPDATE_CUSTOMER_TOP                .      " Global Data
8
9  * INCLUDE Z_UPDATE_CUSTOMER_O01              .      " PBO-Modules
10 * INCLUDE Z_UPDATE_CUSTOMER_I01              .      " PAI-Modules
11 * INCLUDE Z_UPDATE_CUSTOMER_F01              .      " FORM-Routines
12
13
14 INCLUDE z_update_example_status_010o01.
15
16 INCLUDE z_update_example_user_commai01.
```

Include Z_UPDATE_CUSTOMER_TOP Active

```
1  * &-----*
2  * & Include Z_UPDATE_CUSTOMER_TOP            - Module Pool      Z_
3  * &-----*
4  PROGRAM z_update_example.
5  TABLES zcustomer.
6  DATA: ok_code      LIKE sy-ucomm, wa_zcustomer TYPE zcustomer.
```

Include	Z_UPDATE_EXAMPLE_STATUS_010001	Active
---------	--------------------------------	--------

Z_UPDATE_EXAMPLE_STATUS_010001 Active

Active

```

1  *-----
2  ***INCLUDE Z_UPDATE_EXAMPLE_STATUS_010001.
3  *-----
4  *&-----
5  *& Module STATUS_0100 OUTPUT
6  *&-----
7  *&
8  *&-----
9  MODULE status_0100 OUTPUT.
10 SET PF-STATUS '100'.
11 SET TITLEBAR '100'.
12 ENDMODULE.

```

Pattern Pretty Printer Text Elements

Include Z_UPDATE_EXAMPLE_USER_COMMAI01 Active

```
1  *-----
2  ***INCLUDE Z_UPDATE_EXAMPLE_USER_COMMAI01.
3  *-----
4  *&-----
5  *&      Module  USER_COMMAND_0100  INPUT
6  *&-----
7  *      text
8  *-----
9  MODULE user_command_0100 INPUT.
10
11  CASE ok_code.
12  WHEN 'SEARCH'.
13      CALL FUNCTION 'Z_UPDATE_CUST'
14      EXPORTING
15          p_id      = zcustomer-id
16      IMPORTING
17          p_name    = zcustomer-name.
18  WHEN 'UPDATE'.
19      CALL FUNCTION 'Z_UPDATE_CUST2'
20      EXPORTING
21          p_id      = zcustomer-id
22          p_name    = zcustomer-name.
23
24
25  WHEN 'BACK'.
26      LEAVE PROGRAM.
27  ENDCASE.
28
29
30
31  ENDMODULE.
```

Descri...
Report Z_F ▲
Report Z_II ▼
Report Z_II
Program Z_
Include Z_
Report Z_S
Report Z_S
Program Z_
Program Z_

Function module **Z_UPDATE_CUST** Active

Attributes Import Export Changing Tables Exceptions Source code

```
1 FUNCTION z_update_cust.  
2  """-----  
3  """Local Interface:  
4  """ IMPORTING  
5  """   REFERENCE(P_ID) TYPE  ZCUSTOMER-ID  
6  """   EXPORTING  
7  """   REFERENCE(P_NAME) TYPE ZCUSTOMER-NAME  
8  """-----  
9  DATA: zcustomer_wa TYPE zcustomer,  
10         zcustomer_tab TYPE TABLE OF zcustomer.  
11  SELECT SINGLE * FROM zcustomer INTO zcustomer_wa WHERE id = p_id.  
12  p_name = zcustomer_wa-name.  
13  
14  
15  
16  
17  
18 ENDFUNCTION.
```

Function module **Z_UPDATE_CUST2** Active

Attributes Import Export Changing Tables Exceptions Source code

```
1 FUNCTION Z_UPDATE_CUST2.  
2  """-----  
3  """Local Interface:  
4  """ IMPORTING  
5  """   REFERENCE(P_ID) TYPE  ZCUSTOMER-ID  
6  """   REFERENCE(P_NAME) TYPE ZCUSTOMER-NAME  
7  """-----  
8  
9  
10  
11 UPDATE zcustomer SET name = p_name WHERE id = p_id.  
12  
13  
14  
15  
16 ENDFUNCTION.
```