


LAB 1 – 9/10/2024

9/10

Date / /201

Expt. 01 :

3. ~~Connect~~ PCs & Router



Aim – To connect 2 PCs belonging to different networks using a router.



Topology – 2 PCs are connected to each other using copper cross-over cable through the router.

Router (Router0) with two interfaces:

- Interface Fa0/0: IP address 10.0.0.1
- Interface Fa1/0: IP address 20.0.0.1

PC0 connected to Fa0/0 of the router:

- IP address 10.0.0.10
- Default Gateway: 10.0.0.1



IOS Command Line Interface

```
Router>enable
Router#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#interface fastethernet 0/0
Router(config-if)#ip address 10.0.0.2 255.0.0.0
Router(config-if)#no shutdown

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet0/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/0, changed
state to up

Router(config-if)#exit
Router(config)#interface fastethernet 1/0
Router(config-if)#ip address 20.0.0.2 255.0.0.0
Router(config-if)#no shut

Router(config-if)#
%LINK-5-CHANGED: Interface FastEthernet1/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet1/0, changed
state to up

Router(config-if)#exit
Router(config)#exit
Router#
%SYS-5-CONFIG_I: Configured from console by console

Router#show ip route
Codes: C - connected, S - static, I - IGRP, R - RIP, M - mobile, B - BGP
       D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
       N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
       E1 - OSPF external type 1, E2 - OSPF external type 2, E - EGP
       i - IS-IS, L1 - IS-IS level-1, L2 - IS-IS level-2, ia - IS-IS
inter area
       * - candidate default, U - per-user static route, o - ODR
       P - periodic downloaded static route

Gateway of last resort is not set

C    10.0.0.0/8 is directly connected, FastEthernet0/0
C    20.0.0.0/8 is directly connected, FastEthernet1/0
Router#
```

Copy

Paste

