

```
meta [In esecuzione] - Oracle VM VirtualBox
File Macchina Visualizza Inserimento Dispositivi Aiuto
GNU nano 2.0.7 File: /etc/exports

# /etc/exports: the access control list for filesystems which may be exported
# to NFS clients.  See exports(5).
#
# Example for NFSv2 and NFSv3:
# /srv/homes hostname1(rw,sync) hostname2(ro,sync)
#
# Example for NFSv4:
# /srv/nfs4 gss/krb5i(rw,sync,fsid=0,crossmnt)
# /srv/nfs4/homes gss/krb5i(rw,sync)
#

/mnt/newdisk 192.168.50.101(rw,sync,no_root_squash,no_subtree_check)

[ Read 12 lines ]
^G Get Help ^O WriteOut ^R Read File ^Y Prev Page ^K Cut Text ^C Cur Pos
^X Exit ^J Justify ^W Where Is ^V Next Page ^U UnCut Text ^T To Spell
CTRL (DESTRA)
```

```
meta [In esecuzione] - Oracle VM VirtualBox
File Macchina Visualizza Inserimento Dispositivi Aiuto

[ Read 12 lines ]

msfadmin@metasploitable:~$ sudo su
root@metasploitable:/home/msfadmin# msfadmin
bash: msfadmin: command not found
root@metasploitable:/home/msfadmin# ufw enable
Firewall started and enabled on system startup
root@metasploitable:/home/msfadmin# ufw default allow
Default policy changed to 'allow'
(be sure to update your rules accordingly)
root@metasploitable:/home/msfadmin# ufw deny 1524
Rule added
root@metasploitable:/home/msfadmin# ufw status
Firewall loaded

To Action From
--
1524:tcp DENY Anywhere
1524:udp DENY Anywhere

root@metasploitable:/home/msfadmin#
```

```
meta [In esecuzione] - Oracle VM VirtualBox
File  Macchina  Visualizza  Inserimento  Dispositivi  Aiuto

disable          Disables the firewall
default ARG      set default policy to ALLOW or DENY
logging ARG      set logging to ON or OFF
allowdeny RULE   allow or deny RULE
delete allowdeny RULE delete the allow/deny RULE
status           show firewall status
version          display version information

root@metasploitable:/home/msfadmin# ufw deny 139
Rule added
root@metasploitable:/home/msfadmin# ufw deny 445
Rule added
root@metasploitable:/home/msfadmin# ufw status
Firewall loaded

To                Action From
--                -
1524:tcp          DENY  Anywhere
1524:udp          DENY  Anywhere
139:tcp           DENY  Anywhere
139:udp           DENY  Anywhere
445:tcp           DENY  Anywhere
445:udp           DENY  Anywhere

root@metasploitable:/home/msfadmin#
```