

## GUI\_ProjectDelete – Delete a Project

### Revision History

2017-06-21	Robin Lamacraft	Initial creation
2019-04-02	Don Ferguson	Remove Output icon and specifications for it; Replace mockup with actual draft screen image; Renumber 03.6x module references to 05.8x
2020-02-28	Don Ferguson	Align with actual code (Build 19)
2023-07-15	Don Ferguson	Align with Build 30

### SCOPE

This GUI module is called from the Main Menu to delete an existing project.

### PROJECT FILE-SET

A set of files required for normal use of HRE projects consists of:

- an H2 database
- A 'User' Auxiliary file
- folders of external files (images, etc) [optional].

Refer to *03.32 Overview – Auxiliary (Non Database) Files* for details.

### NOTES

The following are generally applicable to project deletions:

- only a User with appropriate RIGHTS can delete a project (see below)
- where a project is deleted, the H2 Database is optionally deleted
- external files are not impacted by the project Delete process. Any action on these rests with either the User or Administrator
- the project record is deleted from the User Auxiliary file
- in the Client-Server model, the Server will:
  - Inform (by message) all Users who have access rights to the project, maintaining that record until the User Client again logs into the Server
  - retain a record of the need to amend User Auxiliary files on a Client, until the next login, when that action is taken.

Further amendment of this specification is foreseen to further define the Server-Administrator processes around the Project Delete functionality.

### LOOK AND FEEL

The window has several parts:

- The upper right icon buttons provide the following universal features:
  - the 'Help' icon displays context Help about the use of this window.
- The "Summary" button opens the ProjectSummary module to display the details of the selected project
- The "Delete" button initiates the deletion of the chosen project
- The "Cancel" button forces exit without a project deletion action.

Project Delete

Available Projects

Project Name	Filename	Local/Remote
HRE Sample Project	HRE Sample database v16d	Local

Selected Project

Project Name

Project Filename

Location

Summary Cancel Delete

PROJECT DELETE Window – Initial view

Project Delete

Available Projects

Project Name	Filename	Local/Remote
HRE Sample Project	HRE Sample database v16d	Local

Selected Project

Project Name HRE Sample Project

Project Filename HRE Sample database v16d

Location Local

Summary Cancel Delete

PROJECT DELETE Window – file chosen view