

File created: 2-Aug-89 13:35:49 {DSK}<LISPPFILES>PS>PS-RS232.;1

changes to: (VARS PS-RS232COMS)
(PROPS (PS-RS232 MAKEFILE-ENVIRONMENT)
(PS-RS232 PRINTERTYPE)
(PS-RS232 SPOOLFILE))
(FNS PS-RS232-AFTERLOGOUT PS-RS232-INIT)

Read Table: INTERLISP

Package: INTERLISP

Format: XCCS

;;
;; Copyright (c) 1989 by Beckman Instruments, Inc. All rights reserved.

(RPAQQ **PS-RS232COMS**

((FILES POSTSCRIPTSTREAM (SYSLOAD FROM LISPUSERS)
DLRS232C)
(INITVARS (PS-RS232-BAUD 9600)
(PS-RS232-DATABITS 8)
(PS-RS232-PARITY 'NONE)
(PS-RS232-STOPBITS 1)
(PS-RS232-FLOWCONTROL 'XOnXOff))
(FNS PS-RS232-AFTERLOGOUT PS-RS232-INIT)
(ADDVARS (DEFAULTPRINTINGHOST PS-RS232)
(AROUNDEXITFNS PS-RS232-AFTERLOGOUT))
(P (PS-RS232-INIT))
(PROP (MAKEFILE-ENVIRONMENT PRINTERTYPE SPOOLFILE)
PS-RS232))

(FILESLOAD POSTSCRIPTSTREAM (SYSLOAD FROM LISPUSERS)
DLRS232C)

(RPAQ? **PS-RS232-BAUD** 9600)

(RPAQ? **PS-RS232-DATABITS** 8)

(RPAQ? **PS-RS232-PARITY** 'NONE)

(RPAQ? **PS-RS232-STOPBITS** 1)

(RPAQ? **PS-RS232-FLOWCONTROL** 'XOnXOff)

(DEFINEQ

(PS-RS232-AFTERLOGOUT

[LAMBDA (EVENT)
(if (EQ EVENT 'AFTERLOGOUT)
then (RS232C.INIT PS-RS232-BAUD PS-RS232-DATABITS PS-RS232-PARITY PS-RS232-STOPBITS PS-RS232-FLOWCONTROL
1)
])

(PS-RS232-INIT

[LAMBDA NIL
[PUTPROP 'PS-RS232 'SPOOLOPTIONS `((BaudRate ,PS-RS232-BAUD)
(BitsPerSerialChar ,PS-RS232-DATABITS)
(Parity ,PS-RS232-PARITY)
(NoOfStopBits ,PS-RS232-STOPBITS)
(FlowControl ,PS-RS232-FLOWCONTROL]
(**PS-RS232-AFTERLOGOUT** 'AFTERLOGOUT) ; Fake it
NIL])

)

(ADDTovar **DEFAULTPRINTINGHOST** PS-RS232)

(ADDTovar **AROUNDEXITFNS** PS-RS232-AFTERLOGOUT)

(PS-RS232-INIT)

(PUTPROPS **PS-RS232 MAKEFILE-ENVIRONMENT** (:READTABLE "INTERLISP" :PACKAGE "INTERLISP"))

(PUTPROPS **PS-RS232 PRINTERTYPE** POSTSCRIPT)

(PUTPROPS **PS-RS232 SPOOLFILE** "{RS232}FOO.PS")

(PUTPROPS **PS-RS232 COPYRIGHT** ("Beckman Instruments, Inc" 1989))

FUNCTION INDEX

PS-RS232-AFTERLOGOUT	1	PS-RS232-INIT	1
----------------------------	---	---------------------	---

VARIABLE INDEX

AROUNDEXITFNS	1	PS-RS232-BAUD	1	PS-RS232-FLOWCONTROL	1	PS-RS232-STOPBITS	1
DEFAULTPRINTINGHOST	1	PS-RS232-DATABITS	1	PS-RS232-PARITY	1		

PROPERTY INDEX

PS-RS232	1
----------------	---