


AWS Day 3 Projects LetsUpgrade


Deploying a nginx in Linux Instance

Step1 : Launch a Instance

Aws console-> Instances -> Launch Instance



Step 2: Choose an AMI for Linux machine



Step 3 : Choose Instance type of free tier eligible

Step 2: Choose an Instance Type
Amazon EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications. [Learn more](#) about instance types and how they can meet your computing needs.

Filter by: **All Instance types** **Current generation** [Show/Hide Columns](#)

Currently selected: t2.micro (Variable ECUs, 1 vCPUs, 2.5 GHz, Intel Xeon Family, 1 GiB memory, EBS only)

	Family	Type	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance	IPv6 Support
<input type="checkbox"/>	General purpose	t2.nano	1	0.5	EBS only	-	Low to Moderate	Yes
<input checked="" type="checkbox"/>	General purpose	t2.micro <small>Free tier eligible</small>	1	1	EBS only	-	Low to Moderate	Yes
<input type="checkbox"/>	General purpose	t2.small	1	2	EBS only	-	Low to Moderate	Yes
<input type="checkbox"/>	General purpose	t2.medium	2	4	EBS only	-	Low to Moderate	Yes
<input type="checkbox"/>	General purpose	t2.large	2	8	EBS only	-	Low to Moderate	Yes

[Cancel](#) [Previous](#) [Review and Launch](#) **Next: Configure Instance Details**

Feedback English (US) © 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. [Privacy Policy](#) [Terms of Use](#)

Step 4 : Give Instance Details

Step 3: Configure Instance Details
Configure the instance to suit your requirements. You can launch multiple instances from the same AMI, request Spot instances to take advantage of the lower pricing, assign an access management role to the instance, and more.

Number of instances: [Launch into Auto Scaling Group](#)

Purchasing option: ☐ Request Spot instances

Network: [Create new VPC](#)

Subnet: [Create new subnet](#)

Auto-assign Public IP:

Placement group: ☐ Add instance to placement group

Capacity Reservation:

IAM role: [Create new IAM role](#)

Shutdown behavior:

[Cancel](#) [Previous](#) [Review and Launch](#) **Next: Add Storage**

Feedback English (US) © 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. [Privacy Policy](#) [Terms of Use](#)

Step 5 : Give Storage details

Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. [Learn more](#) about storage options in Amazon EC2.

Volume Type	Device	Snapshot	Size (GiB)	Volume Type	IOPS	Throughput (MB/s)	Delete on Termination	Encryption
Root	/dev/xvda	snap-00a3ac8046ab803ef	8	General Purpose SSD (gp2)	100 / 3000	N/A	<input checked="" type="checkbox"/>	Not Encrypted

[Add New Volume](#)

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage. [Learn more](#) about free usage tier eligibility and usage restrictions.

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Add Tags](#)

Feedback English (US) © 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy Policy Terms of Use

Step 6 : Give the tags(gives the name of the machine)

Step 5: Add Tags

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver. A copy of a tag can be applied to volumes, instances or both. Tags will be applied to all instances and volumes. [Learn more](#) about tagging your Amazon EC2 resources.

Key (128 characters maximum)	Value (256 characters maximum)	Instances	Volumes
Name	Linux	<input checked="" type="checkbox"/>	<input checked="" type="checkbox"/>

[Add another tag](#) (Up to 50 tags maximum)

[Cancel](#) [Previous](#) [Review and Launch](#) [Next: Configure Security Group](#)

https://us-east-2.console.aws.amazon.com/console/home?region=us-east-2 © 2008 - 2020, Amazon Internet Services Private Ltd. or its affiliates. All rights reserved. Privacy Policy Terms of Use

Step 7 : Give the security group details

Step 6: Configure Security Group

A security group is a set of firewall rules that control the traffic for your instance. On this page, you can add rules to allow specific traffic to reach your instance. For example, if you want to set up a web server and allow Internet traffic to reach your instance, add rules that allow unrestricted access to the HTTP and HTTPS ports. You can create a new security group or select from an existing one. [Learn more](#) about Amazon EC2 security groups.

Assign a security group: ☒ Create a new security group
☐ Select an existing security group

Security group name:

Description:

Type	Protocol	Port Range	Source	Description
All traffic	All	0 - 65535	Anywhere 0.0.0.0/0, ::/0	e.g. SSH for Admin Desktop

[Add Rule](#)

Warning

Rules with source of 0.0.0.0/0 allow all IP addresses to access your instance. We recommend setting security group rules to allow access from known IP addresses only.

[Cancel](#) [Previous](#) [Review and Launch](#)

Step 8 : Check the details and launch

Step 7: Review Instance Launch

Please review your instance launch details. You can go back to edit changes for each section. Click **Launch** to assign a key pair to your instance and complete the launch process.

Improve your instances' security. Your security group, launch-wizard-3, is open to the world. Your instances may be accessible from any IP address. We recommend that you update your security group rules to allow access from known IP addresses only. You can also open additional ports in your security group to facilitate access to the application or service you're running, e.g., HTTP (80) for web servers. [Edit security groups](#)

AMI Details [Edit AMI](#)

Amazon Linux 2 AMI (HVM), SSD Volume Type - ami-07c8bc6c1ce8598c3

Amazon Linux 2 comes with five years support. It provides Linux kernel 4.14 tuned for optimal performance on Amazon EC2, systemd 219, GCC 7.3, Glibc 2.26, Binutils 2.29.1, and the latest software packages through extras.


Root Device Type: ebs Virtualization type: hvm

Instance Type [Edit instance type](#)


Instance Type	ECUs	vCPUs	Memory (GiB)	Instance Storage (GB)	EBS-Optimized Available	Network Performance
t2.micro	Variable	1	1	EBS only		Low to Moderate

[Cancel](#) [Previous](#) [Launch](#)


Step 9 : Choose the existing keypair(.pem file which gives the password) if already exists. and launch instance



Step 10 : When launching of the machine has been initiated with the id




**Step 11 : Now the linux machine has been created and conformed by the status shown
2/2 check**




Step 12 : In the meanwhile download MobaXterm to connect the linux machine with the Home Edition V20.3 (Portable Edition). To know the username of the machine . Select the machine

connect->



Step 13 : Open the MobaXterm Application


Session-> SSH -> Enter the host(Public ip) -> Specify Username(ec2-user for)



Step 15 : Now the machine has been connected. and then update settings and install nginx

sudo apt-get -y update

sudo apt-get -y install nginx



Here the setting is not updated. Some issues in this may be due to xll forwarding.