



Steps to fix Currency and Date format.


1. First Open Control Panel.




2. It might be opened in 2 different forms. Click on the Region if all items are displayed as below and skip to Step 5.



3. Click “Clock and Region”



4. Click “Change date time or number formats”



5. Change the date to the given format below . To change Currency click Additional Settings .

The screenshot shows the 'Region' dialog box with the 'Formats' tab selected. The 'Format' dropdown is set to 'English (United States)'. Under 'Language preferences', the 'Date and time formats' section shows the following settings: Short date: dd/MM/yyyy, Long date: dddd, MMMM d, yyyy, Short time: h:mm tt, Long time: h:mm:ss tt, and First day of week: Sunday. An 'Additional settings...' button is highlighted in yellow. At the bottom are 'OK', 'Cancel', and 'Apply' buttons.

Region

Formats Location Administrative

Format:
English (United States)

[Language preferences](#)

Date and time formats

Short date: dd/MM/yyyy

Long date: dddd, MMMM d, yyyy

Short time: h:mm tt

Long time: h:mm:ss tt

First day of week: Sunday

Examples

Short date: 11/06/2019

Long date: Tuesday, June 11, 2019

Short time: 9:42 PM

Long time: 9:42:10 PM

Additional settings...

OK Cancel Apply

6. Remove the value and press SPACEBAR and press apply and OK.

The screenshot shows the 'Customize Format' dialog box with the 'Currency' tab selected. The 'Example' section shows 'Positive: 123,456,789.00' and 'Negative: (123,456,789.00)'. The 'Currency symbol' dropdown is highlighted in yellow and shows a blank space. Other settings include 'Positive currency format: 1.1', 'Negative currency format: (1.1)', 'Decimal symbol: .', 'No. of digits after decimal: 2', 'Digit grouping symbol: ,', and 'Digit grouping: 123,456,789'. At the bottom, there is a 'Reset' button and 'OK', 'Cancel', and 'Apply' buttons, with 'OK' and 'Apply' highlighted in yellow.

Customize Format

Numbers **Currency** Time Date

Example

Positive: 123,456,789.00 Negative: (123,456,789.00)

Currency symbol:

Positive currency format: 1.1

Negative currency format: (1.1)

Decimal symbol: .

No. of digits after decimal: 2

Digit grouping symbol: ,

Digit grouping: 123,456,789

Click Reset to restore the system default settings for numbers, currency, time, and date.

Reset

OK Cancel Apply