

Nuke CTL Plugin User Documentation

Color Transform Language, or CTL, is a programming language developed as a building block for digital color management. The Nuke CTL plugin allows for CTL use and modifications within the Nuke compositing environment.

1. Loading Plugin


Before using the plugin make sure that the file, NukeCtl.dylib, is installed in the correct directory. This is usually the .nuke folder located in your home directory, but could differ if your NUKE_PATH environment variable is set. Note that the .nuke directory is hidden by default.

For more help on installing plugins, please see the Nuke documentation.

http://docs.thefoundry.co.uk/nuke/63/pythondevguide/installing_plugins.html

If you would like to add the node into Nuke's menu system, please copy the following two lines into Nuke's menu.py script. This script will be called when Nuke starts.

```
toolbar = nuke.menu('Nodes')
toolbar.addCommand('Color/CTL', 'nuke.createNode("NukeCtl")')
```



Menu.py must reside in one of Nuke's plugin path directories and may have to be created. More information can be found here.

<http://docs.thefoundry.co.uk/nuke/63/pythondevguide/startup.html>

Once the plugin is installed in the correct folder, click on the CTL node from the Color menu. Note that the node will only be visible if menu.py was modified following the above instructions. Otherwise press "x" within Nuke to open the command prompt. Enter "NukeCtl" to load the plugin into your workspace. The node has six main knobs: Set Module Path, Module Path Read CTL File, CTL Text, Input Parameters, and Write CTL File.

Create a read node and drag the output arrow onto the CTL node to set the input channels. Drag the output channels onto the viewer or another node to set the output channels.

2. Reading a file

To read a CTL file, click on the folder icon in the "Read CTL File" knob. Select the appropriate CTL file in the file browser and click open. The text data will be loaded into the CTL Text knob. If the file has the appropriate syntax, the transformation will be applied to the image, otherwise an error will be output to the Error Console.

3. Modifying Text

The CTL Text knob displays the text of the current CTL file being processed. This text can also be modified and saved. Once the text has been modified in the knob, click "Write CTL File" and select the filename to save. If the file already exists, the user will be asked if they would like to overwrite the file. To undo or redo a text modification click on Edit->Undo or Edit->Redo and save the file.

4. Input Parameters

The "Input Parameters" knob displays input parameters specified by the user. By default rIn, gIn, bIn, rOut, gOut, bOut, and aOut must be present, but other variables may be added to be processed in the CTL functions. These variables will be automatically detected by the plugin and will appear in this knob. The user can then modify the default value of 0, and see the updated results. If an input parameter is an array then a 0 will be output for each element of the array.

Note: If an input parameter is added for modified, reload the file following step 2. When reading a file, the plugin allocates memory for each input parameter. If the parameters in the CTL text are modified and not reloaded, Nuke may try to access unreserved memory and crash.

5. Module Path

CTL has the ability to import utility files from a different directory. By default, the utilities directory is found by setting the CTL_MODULE_PATH environment variable. A case may arise where different utility directories need to be accessed by multiple CTL node instances. Manually setting the module path per node resolves this issue. To set the CTL module path, check the "Set Module Path" knob. Once the "Module Path" knob become accessible, navigate to the utilities directory by clicking on the folder icon. Once the directory is reached click on the Open button to override the default module path.

Paths can also be accessed by manually typing the path into the knob. Multiple paths can be set by separating the paths by a colon (Mac) or a semicolon (Windows). For example, multiple paths could be set by typing `"/Users/admin/ctl_transforms:/Users/admin/ctl_transforms/utilities"` into the knob.

Unchecking the "Set Module Path" will default the module path back to the CTL_MODULE_PATH environment variable and will cause the "Module Path" knob to be disabled. The "Set Module Path" knob is disabled by default.

6. Masking

Masking can be applied by creating a roto node and piping its output into the mask channel of the NukeCtl node.

7. Known Issues

Currently the plugin may crash Nuke by switching the "Channels" knob attribute. If an issue is found please report to <https://github.com/ampas/CTL/issues>