


Nama : Alfi Dimar Pradana

NIM : L200160101


MODUL 3

1. Setting Wifi untuk Accespoint :


Masuk ke menu konfigurasi dengan address 192.168.1.254 (defaultnya 192.168.1.50)




Memilih opsi sebagai accespoint dan mengganti IP addressnya



Memberi IP di PC dengan network yang sama dengan accespoint



Tes ping ke IP dari accespoint teman



2. Pont-to-Point

Masuk ke menu konfigurasi dengan address 192.168.1.1

EnGenius® Wireless Outdoor Access Point/ Client Bridge

Client Bridge

Status

- Main
- Connection Status
- System Log

System

- System Properties
- IP Settings
- Spanning Tree Settings

Wireless

- Wireless Network
- Wireless Security
- Wireless Advanced Settings

Management

- Administration
- SNMP Settings
- Auto Reboot Settings
- Backup/Restore Settings
- Firmware Upgrade
- Time Settings
- Log
- Diagnostics

Wireless Network

Home Reset

Wireless Mode: 802.11b/g Mixed (2GHz/54Mbps)

Specify the static SSID : ROZAQUE TEAM (1 to 32 characters)
Or press the button to search for any available WLAN Service.
Site Survey

Prefer BSSID: ☐ E8 ☐ DE ☐ 27 ☐ B7 ☐ F6 ☐ 78

WDS Client: ☒ Enable ☐ Disable

Apply Cancel

Beri IP satu network dengan accespoint sebelumnya

EnGenius® Wireless Outdoor Access Point/ Client Bridge

Client Bridge

Status

- Main
- Connection Status
- System Log

System

- System Properties
- IP Settings
- Spanning Tree Settings

Wireless

- Wireless Network
- Wireless Security
- Wireless Advanced Settings

Management

- Administration
- SNMP Settings
- Auto Reboot Settings
- Backup/Restore Settings
- Firmware Upgrade
- Time Settings
- Log
- Diagnostics

System Information

Device Name: EOC2611P

Ethernet MAC Address: 00:02:6f:94:4d:e6

Wireless MAC Address: 00:02:6f:94:4d:e7

Country: N/A

Current Time: Sat Jan 1 07:43:06 UTC 2000

Device Uptime: 0 Days 0 Hours 43 Mins

Firmware Version: 1.3.1

Auto Reboot Settings: Disabled

LAN Settings

IP Address: 192.168.1.1

Subnet Mask: 255.255.255.0

Default Gateway: 0.0.0.0

DHCP Client: Disabled

Current Wireless Settings

Operation Mode: Client Bridge

Wireless Mode: IEEE 802.11b/g Mixed

Frequency/Channel: 2.412GHz (Channel 01)

Wireless Network Name (SSID): ROZAQUE TEAM


Security: Disabled

Spanning Tree Protocol: Disabled


Distance: 1 Km

Refresh

Pilih mode ClientBridge



Beri IP satu network dengan point-to-point sebelumnya



Tes ping ke IP dari accespoint teman

